



Configuring Ensemble Productions

Version 2018.1
2024-05-02

Configuring Ensemble Productions
Ensemble Version 2018.1 2024-05-02
Copyright © 2024 InterSystems Corporation
All rights reserved.

InterSystems®, HealthShare Care Community®, HealthShare Unified Care Record®, IntegratedML®, InterSystems Caché®, InterSystems Ensemble®, InterSystems HealthShare®, InterSystems IRIS®, and TrakCare are registered trademarks of InterSystems Corporation. HealthShare® CMS Solution Pack™ HealthShare® Health Connect Cloud™, InterSystems IRIS for Health™, InterSystems Supply Chain Orchestrator™, and InterSystems TotalView™ For Asset Management are trademarks of InterSystems Corporation. TrakCare is a registered trademark in Australia and the European Union.

All other brand or product names used herein are trademarks or registered trademarks of their respective companies or organizations.

This document contains trade secret and confidential information which is the property of InterSystems Corporation, One Memorial Drive, Cambridge, MA 02142, or its affiliates, and is furnished for the sole purpose of the operation and maintenance of the products of InterSystems Corporation. No part of this publication is to be used for any other purpose, and this publication is not to be reproduced, copied, disclosed, transmitted, stored in a retrieval system or translated into any human or computer language, in any form, by any means, in whole or in part, without the express prior written consent of InterSystems Corporation.

The copying, use and disposition of this document and the software programs described herein is prohibited except to the limited extent set forth in the standard software license agreement(s) of InterSystems Corporation covering such programs and related documentation. InterSystems Corporation makes no representations and warranties concerning such software programs other than those set forth in such standard software license agreement(s). In addition, the liability of InterSystems Corporation for any losses or damages relating to or arising out of the use of such software programs is limited in the manner set forth in such standard software license agreement(s).

THE FOREGOING IS A GENERAL SUMMARY OF THE RESTRICTIONS AND LIMITATIONS IMPOSED BY INTERSYSTEMS CORPORATION ON THE USE OF, AND LIABILITY ARISING FROM, ITS COMPUTER SOFTWARE. FOR COMPLETE INFORMATION REFERENCE SHOULD BE MADE TO THE STANDARD SOFTWARE LICENSE AGREEMENT(S) OF INTERSYSTEMS CORPORATION, COPIES OF WHICH WILL BE MADE AVAILABLE UPON REQUEST.

InterSystems Corporation disclaims responsibility for errors which may appear in this document, and it reserves the right, in its sole discretion and without notice, to make substitutions and modifications in the products and practices described in this document.

For Support questions about any InterSystems products, contact:

InterSystems Worldwide Response Center (WRC)
Tel: +1-617-621-0700
Tel: +44 (0) 844 854 2917
Email: support@InterSystems.com

Table of Contents

| | |
|---------------------------------------------------------------|-----------|
| About This Book | 1 |
| 1 Introduction to Configuration Tasks | 3 |
| 1.1 Background for System Administrators | 3 |
| 1.2 Introduction to Settings | 4 |
| 1.3 Possible Configuration Tasks | 4 |
| 1.4 Accessing the Configuration Options | 5 |
| 1.5 Accessing Management Options | 5 |
| 2 Creating a Production | 7 |
| 2.1 Creating a Production | 7 |
| 2.2 Opening a Production | 8 |
| 2.2.1 Introduction to the Production Configuration Page | 8 |
| 2.2.2 The Update Button | 9 |
| 2.3 Controlling the Display | 9 |
| 2.3.1 Filtering the Display by Category | 9 |
| 2.3.2 Sorting Business Hosts | 10 |
| 2.3.3 Choosing a View Type | 10 |
| 2.3.4 Controlling the Refresh | 11 |
| 2.4 Understanding the Color Coding | 11 |
| 2.5 Starting a Production | 12 |
| 2.6 Stopping a Production | 13 |
| 2.7 Exporting a Production | 13 |
| 2.8 Generating Production Documentation | 13 |
| 2.9 Deleting a Production | 14 |
| 2.10 Using the Production List | 14 |
| 3 Adding Business Hosts | 17 |
| 3.1 Introduction | 17 |
| 3.2 Configuration Names | 18 |
| 3.3 Adding Business Hosts to a Production | 18 |
| 3.4 Wizard Options | 18 |
| 3.5 Options in the Business Service Wizard | 19 |
| 3.6 Options in the Business Process Wizard | 20 |
| 3.7 Options in the Business Operation Wizard | 21 |
| 3.8 Enabling, Disabling, or Restarting a Business Host | 22 |
| 3.9 Changing the Class That a Business Host Uses | 22 |
| 3.10 Copying a Business Host | 22 |
| 3.11 Deleting a Business Host | 23 |
| 3.12 Repairing an Error | 23 |
| 3.13 Viewing and Configuring Connections | 24 |
| 3.14 Working with Multiple Versions of a Business Host | 24 |
| 4 Configuring Settings | 27 |
| 4.1 Configuring Settings | 27 |
| 4.2 Understanding the Color Coding for Settings | 28 |
| 4.3 Searching for a Setting | 28 |
| 4.4 Getting Help for Settings | 28 |
| 4.5 Restoring a Setting to Its Default Value | 28 |

| | |
|--------------------------------------------------------------------------|-----------|
| 5 Configuring Alerts | 31 |
| 5.1 About Alerts | 31 |
| 5.2 Configuring an Alert Processor | 32 |
| 5.3 Configuring Alerts on Errors | 32 |
| 5.4 Configuring Alerts on Queue Buildups | 32 |
| 5.5 Other System Alerts | 32 |
| 6 Defining Reusable Items for Use in Settings | 35 |
| 6.1 Defining Business Partners | 35 |
| 6.2 Defining Credentials | 36 |
| 6.3 Defining Schedule Specifications | 37 |
| 6.3.1 Schedule Specifications | 37 |
| 6.3.2 Examples | 38 |
| 6.3.3 Scheduling and Daylight Saving Time | 38 |
| 6.3.4 Intended Use and Limitations | 39 |
| 7 Defining Other Options for Ensemble | 41 |
| 7.1 Defining Data Lookup Tables | 41 |
| 7.1.1 Lookup Table File Format | 43 |
| 7.1.2 Importing Flat Files as Data Lookup Tables | 43 |
| 7.2 Defining System Default Settings | 44 |
| 7.2.1 Purpose of System Default Settings | 44 |
| 7.2.2 Accessing the System Default Settings | 44 |
| 7.2.3 Creating or Editing a System Default Setting | 45 |
| 7.3 Configuring Source Control Settings | 47 |
| 8 Configuring the Enterprise Message Bank | 49 |
| 8.1 Configuring the Message Bank Link | 49 |
| 8.2 Configuring a Client Production to Send Messages | 50 |
| 8.2.1 Configuring a Message Bank Business Operation | 50 |
| 8.2.2 Details for the Archive Items Setting | 51 |
| 8.3 Configuring the Message Bank Service on the Server | 52 |
| 9 Identifying Enterprise Systems for Viewing and Monitoring | 53 |
| 10 Creating Dashboards | 55 |
| 10.1 Introduction to Dashboards | 55 |
| 10.2 Creating Dashboards | 57 |
| 10.3 Location of Dashboard Definitions | 58 |
| 10.4 For More Information | 58 |
| Settings in All Productions | 59 |
| Settings in All Productions | 60 |
| Settings in All Business Services | 61 |
| Settings in All Business Processes | 65 |
| Settings in All Business Operations | 68 |
| Pool Size and Actor Pool Size | 70 |
| Time Stamp Specifications for Filenames | 72 |

About This Book

This book, which is for developers and system administrators, explains how to use the Management Portal to perform the configuration tasks related to creating an Ensemble production; some of these tasks also apply later when configuring the production for a specific site. It contains the following sections:

- [Introduction to Configuration Tasks](#)
- [Creating a Production](#)
- [Adding Business Hosts](#)
- [Configuring Settings](#)
- [Configuring Alerts](#)
- [Defining Reusable Items for Use in Settings](#)
- [Defining Other Options for Ensemble](#)
- [Configuring the Enterprise Message Bank](#)
- [Identifying Enterprise Systems for Viewing and Monitoring](#)
- [Creating Dashboards](#)
- [Settings in All Productions](#)

For a detailed outline, see the [table of contents](#).

The following books provide related information:

- [*Ensemble Best Practices*](#) describes best practices for organizing and developing Ensemble productions.
- [*Developing Ensemble Productions*](#) explains how to perform the development tasks related to creating an Ensemble production. Many of these tasks require Studio, and this book is intended primarily for developers.
- [*Managing Ensemble*](#) explains how to use the Management Portal to manage Ensemble. This book is intended primarily for system administrators.
- [*Caché System Administration Guide*](#) describes common system administration tasks in a pure Caché environment.
- [*Caché Security Administration Guide*](#) describes authentication, authorization, auditing, managed key encryption, SSL/TLS, and other aspects of Caché security.

For general information, see the *InterSystems Documentation Guide*.

1

Introduction to Configuration Tasks

This book describes how to perform the configuration tasks related to creating an Ensemble production; some of these tasks also apply later when configuring the production for a specific site. This chapter provides some background and an overview of these tasks. It contains the following topics:

- [Background for System Administrators](#)
- [Introduction to Settings](#)
- [Possible Configuration Tasks](#)
- [Accessing the Configuration Options](#)
- [Accessing Management Options](#)

1.1 Background for System Administrators

This book is intended for both developers and system administrators. If you are a system administrator, this section provides some basic terminology to help you get started.

An Ensemble *production* is a specialized package of software and documentation that integrates multiple, potentially disparate software systems. A production includes elements that communicate with these external systems, as well as elements that perform processing that is internal to the production.

A production consists of a number of *business hosts* that communicate with each other (and with external systems). There are three distinct types of business host:

- A *business service* receives input from outside the production.
- A *business process* is responsible for communication and logic that is entirely within the production.
- A *business operation* usually sends output from the production. Business operations can also be used for communication and logic within a given production.

Within a production, all communication is carried out by means of request and response messages between the business hosts.

Ensemble permits only one production to be running in a given namespace at any given time.

A running production continues to run even when you close the Management Portal.

For additional background, see “[Core Concepts](#)” in *Monitoring Ensemble*.

1.2 Introduction to Settings

A major part of configuration is the task of modifying settings. This section provides an introduction.

Settings are configurable values that control the behavior of a production. You can modify these while a production is running and the changes take effect immediately. Settings can affect a production in many ways. For example, a setting can specify:

- The TCP port on which a business service should listen
- How frequently to check for new input.
- The external data source name (DSN) to use.
- The SSL configuration to use when connecting to an external entity.
- How long to stay connected.
- And so on.

You can specify settings separately for the production and for each business host.

Some settings, such as **Actor Pool Size**, **Pool Size** and **Reply Code Actions**, should be decided as part of the production design and usually should not be changed later. Other settings are dependent on the environment, such as TCP/IP addresses or file paths. It is appropriate to modify these settings if the environment changes.

1.3 Possible Configuration Tasks

While you are creating an Ensemble production, you will need to perform the following tasks:

- Creating a production. See “[Creating and Configuring a Production](#).”
- Adding business hosts to the production. See “[Adding Business Hosts to a Production](#).”
- Configuring settings of the production and its business host. See “[Creating and Configuring a Production](#)” and “[Configuring Business Hosts](#).”

You might also perform some or all of the following tasks:

- Configuring reusable items for use in settings: business partners, credentials, and schedule specifications. See “[Defining Reusable Items for Use in Settings](#).”
- Defining other options: data lookup tables, system defaults, and source control settings. See “[Defining Other Options for Ensemble](#).”
- Configuring the Ensemble Message Bank. See “[Configuring the Enterprise Message Bank](#).”
- Creating dashboards to display Ensemble business metrics. See “[Creating Dashboards](#).”

If you are a system administrator, you might be most likely to use the chapters “[Creating and Configuring a Production](#),” “[Configuring Business Hosts](#),” and “[Defining Reusable Items for Use in Settings](#).”

1.4 Accessing the Configuration Options

To configure Ensemble, you use the Management Portal. To access the configuration tools in the Portal:

1. Click **Ensemble**.
2. Click **Configure**.

Ensemble then displays a menu. The following chapters describe how to use the options on this menu.

1.5 Accessing Management Options

Most of this book discusses the Production Configuration page, **Ensemble > Configuration > Production**. This page includes tabs that provide easy access to management options, which are described elsewhere.

If you click **Production Settings** above the diagram, the options apply to the entire production. Similarly, if you click a business host, the options apply to that business host.

These management tabs are as follows:

- **Queue** — Click to view a list of the queues related to this production or business host.
- **Log** — Click to view an abbreviated list of Event Log entries for this production or business host.
- **Messages** — Click to view an abbreviated list of messages processed by this production or business host.
- **Jobs** — Click to view jobs related to this production or business host.

Each these tabs provides a link to a management page (which opens in a new window) with more information. For details on the terminology and tasks, see [Managing Ensemble](#).

On the **Jobs** tab, you can also select a job and perform one of the following actions on it:

- **Abort** the current message being retried for the selected job.
- **Suspend** the current message being retried for the selected job.
- **Stop** the selected job.

2

Creating a Production

The **Production List** page (**Ensemble > List > Productions**) allows you to create a new production and open, export, document, or delete an existing production. After you open a production, Ensemble displays the **Production Configuration** page, which allows you to configure, start, and stop Ensemble productions. If you are not yet working in a production, the **Production Configuration** page allows you to create or open a production. Once you are working in a production, you can use the **Actions** tab to switch to a new or another existing production or to document or export the current one.

This chapter primarily describes how to use these pages. It contains the following topics:

- [Creating a Production](#)
- [Opening a Production](#)
- [Controlling the Display](#)
- [Understanding the Color Coding](#)
- [Starting a Production](#)
- [Stopping a Production](#)
- [Generating Production Documentation](#)
- [Exporting a Production](#)
- [Deleting a Production](#)
- [Using the Production List](#)

Later chapters describe how to [add business hosts](#) and [configure settings](#) for the production and all business hosts.

Note: If a production is Suspended or Troubled, see “[Correcting Production Problem States](#),” in *Monitoring Ensemble*.

2.1 Creating a Production

To create a production:

1. If you are not already in an Ensemble namespace, choose your working namespace from the available Ensemble namespaces.
2. Navigate to the **Ensemble > List > Productions**.
3. Click **New** to create a new production.

4. Enter a **Package Name**, **Production Name**, and **Description**.
5. Choose one of the following:
 - **HL7 Messaging** — If you are using HL7 with Ensemble, choose this option. You can add any generic Ensemble elements that you need as you build the HL7 production, but choosing this option provides a useful set of starter elements for HL7.
 - **Generic** — Choose this option for all other types of production.
6. Click **OK**.
7. Now you can [add business hosts](#) and [configure them](#), as described in later chapters.

2.2 Opening a Production

To open a production:

1. If you are not already in an Ensemble namespace, choose your working namespace from the available Ensemble namespaces.
2. Navigate to the **Ensemble > List > Productions**.
3. Click **Open** to open an existing production.

To open a production or create a new production when you currently configuring a production on the **Production Configuration** page:

1. If you have clicked anywhere within the diagram, click **Production Settings**.


Production Settings

This step returns the focus to the production and changes the options on the **Actions** tab.

2. Click on the **Actions** tab.
3. Click **Open** on the **Actions** tab to open an existing production or click **New** on the same tab to create a new production.

2.2.1 Introduction to the Production Configuration Page

For example, the following figure shows the *Demo.Loan.FindRateProduction* in the ENSDEMO namespace.



2.2.2 The Update Button

While you are developing new code and configuring the production, it sometimes happens that when you start the Management Portal, Ensemble detects a discrepancy between the production as defined in the code, and the status of the running production. Examples would be if:

- A specific business host experienced an error and has died (the most likely cause).
- You changed a configuration parameter for a business host in a running production, such that the host now needs to be restarted.
- You enabled or disabled an item in a production, and this action requires the production to be stopped and restarted.
- A production typically opens a Terminal window, but this window was closed by a user action while the production was still running.


When such discrepancies occur, the **Production Configuration** page displays the **Update** button. Click this, and Ensemble updates the production to resolve the discrepancy.

2.3 Controlling the Display

This section describes how to [filter](#) the display, [sort](#) the display, how to display alternative [views](#) of the production, and how to control the [refresh](#) of the display.

2.3.1 Filtering the Display by Category

To filter the business hosts in the production diagram, use the **Category** list.



Select a value from this list. When you do so, the diagram display only those business hosts that have been assigned to the given category. Or click **All** to view all the business hosts in the production.

Note that a business host can be assigned to multiple categories.

For details, see “[Category](#)” in the reference “[Settings in All Productions](#).”

2.3.2 Sorting Business Hosts

To sort the business hosts in the production diagram, use the **Sort** options:

Sort: **Name** Status Number


- **Name** — Sorts items alphabetically within each column.
- **Status** — Sorts items within each column by status as follows: disabled, enabled, error, inactive.
- **Number** — Sorts items as listed in the production class (which, by default, represents the order in which they were added to the production). To modify this order, you can edit the production class in Studio. See “[Notes on Editing the Production Class](#)” in *Developing Ensemble Productions*.

2.3.3 Choosing a View Type


To view the business hosts in a different way, use the **View** options:




These view types are as follows:

-  The *listing view* displays the business hosts in lists, within the **Services**, **Processes**, and **Operations** columns. This is the view used in most of the documentation.


| Production Running | | |
|-------------------------------------|-------------------------------------------|---------------------------------------|
| Category: All | | |
| Services | Processes | Operations |
| ● Demo.Loan.BankMetrics | ● Demo.Loan.BankEven | ● Demo.Loan.FindRateEMailOperation |
| ● Demo.Loan.FindRateCSPService | ● Demo.Loan.BankManana | ● Demo.Loan.FindRateFileOperation |
| ○ Demo.Loan.FindRateEMailService | ● Demo.Loan.BankSoprano | ○ Demo.Loan.FindRateMQSeriesOperation |
| ● Demo.Loan.FindRateFileService | ● Demo.Loan.BankUS | ○ Demo.Loan.FindRateMSMQOperation |
| ○ Demo.Loan.FindRateMQSeriesService | ● Demo.Loan.FindRateDecisionProcessBPL | ● Demo.Loan.FindRateTCPOperation |
| ○ Demo.Loan.FindRateMSMQService | ● Demo.Loan.FindRateDecisionProcessCustor | ● Demo.Loan.WebOperations |
| ● Demo.Loan.FindRateTCPService | | ● My Terminal Output |
| ● Demo.Loan.FindRateTerminalService | | |

-  The *monitor view* represents each business host in a larger circle where you can easily see items that may need attention. Here, click a circle to see a box with details for the business host.



The *service bus view* is relevant only if you configure [business partners](#) and enter values in the **Business Partner** setting.

This view displays the business hosts grouped by their associated business partners.



2.3.4 Controlling the Refresh







Click the circular arrow to refresh the diagram once or click **on** to reload a fresh copy of the production diagram every 60 seconds; the refresh timer is **off** by default.

Note that Ensemble checks the status of individual business hosts (on a shorter interval) and refreshes the display for individual hosts as needed, regardless of the setting of auto-refresh.

2.4 Understanding the Color Coding

When in list or monitor [view](#), the **Production Configuration** page displays a circular status indicator next to each business host. If you click **Legend** to see the meaning of this indicator, Ensemble displays the following:

Indicators

-  Not running, enabled
-  Running
-  Disabled
-  Error
-  Retrying
-  Inactive

Interaction

Click on an item's name to view its details

Click on an indicator to view the connections

Double-click on an item to enable or disable it

Note: You can increase the visibility of the error states by specifying that the Error, Retry and Inactive states are to be indicated by a colored ellipse, not a circle. To do this append `&VISUALAID=1` to the URL for the Production Configuration page.

2.5 Starting a Production

To start an Ensemble production that is displayed on the **Production Configuration** page:

1. Click **Start** and answer **OK** to launch the **Start Production** dialog box. It displays the name of the production, its startup status, and any messages associated with production startup.

Note: If any Terminal windows open as a result of starting the production, do not close them.

2. When the startup dialog shows it is Done, click **OK** at the bottom of the **Start Production** dialog box.

You can stop the running production and start another one from this page. Only one of these productions can run at a time in a given namespace. If you try to start one, and another is already started, a warning message displays and nothing changes. For example:

```
12:05:06.292:Ens.Director: ERROR <Ens>ErrProductionAlreadyRunning:
Production 'Demo.Loan.FindRateProduction' is already running
12:05:06.352:Ens.Director: ERROR <Ens>ErrProductionAlreadyRunning:
Production 'Demo.Loan.FindRateProduction' is already running
Production 'Demo.Loan.BankUSProduction' not started:
ERROR <Ens>ErrProductionAlreadyRunning: Production
'Demo.Loan.FindRateProduction' is already running
```

Note: This option is primarily for use during development. For a live, deployed production, InterSystems recommends that you use the auto-start option. See “[Starting and Stopping Productions](#)” in *Managing Ensemble*.

2.6 Stopping a Production

To stop an Ensemble production that is displayed on the **Production Configuration** page:

1. Click **Stop** and answer **OK** to launch the **Stop Production** dialog box. It displays the name of the production, its shutdown status, and any messages associated with production shutdown.
2. When the shutdown dialog indicates it is Done, click **OK** at the bottom of the **Stop Production** dialog box.
3. If the request to stop the production initially fails, the portal displays a message:

“Production could not stop, do you want to force a shut down?”

And provides a command:

Yes - Force to Shut Down

If you click this command, the production is forced to shut down.

Ensemble displays an informational message if you try to stop a production that is not running.

2.7 Exporting a Production

To export a production from the **Production Configuration** page:

1. If you have clicked anywhere within the diagram, click **Production Settings**.

Production Settings

This step returns the focus to the production and changes the options on the **Actions** tab.

2. Click **Export** on the **Actions** tab.
3. Select items to export.
4. Click **OK**.

See [Deploying a Production](#) in *Developing Ensemble Productions* for details on exporting and deploying a production.

2.8 Generating Production Documentation

You can navigate to the **Production Documentation** page from the following places in the Management Portal:

- From the **Production List** page (**Ensemble > List > Productions**), select a production name and click **Document**.
- From the **Production Configuration** page (**Ensemble > Configure > Production**), on the **Actions** tab for the production, click **Document**.

From the **Production Documentation** page for a production, you can generate or view the production documentation, which includes a list of all the business hosts and their settings. Perform one of the following actions:

- Click **View** to display the online documentation you previously generated. If you click **View** and no HTML documentation exists, you can choose to generate it.

- Click **Generate** to create new documentation for this production using a background job.

It may take a considerable amount of time to generate documentation for large productions; therefore, you may not want to generate new documentation if you have not made changes to the configuration of your production.

- **Cancel** to cancel the operation and return to the Ensemble menu page.

You can also generate HTML documentation and, additionally, PDF documentation using the following methods in the `Ens.Config.Production` class:

- **CreateDocumentHTML()** — creates new documentation in HTML format.

For example, to create documentation for `Demo.Loan.FindRateProduction` in HTML format:

ObjectScript

```
Set
status=##class(Ens.Config.Production).CreateDocumentHTML("Demo.Loan.FindRateProduction",1,.URL,.ErrLog)
```

- **RemoveDocumentHTML()** — removes existing HTML-format documentation from the current namespace.
- **CreateDocumentPDF()** — creates new documentation as a PDF file.

For example, to create documentation for `Demo.Loan.FindRateProduction` in PDF format, you can use the method in a statement similar to the following:

ObjectScript

```
Set
status=##class(Ens.Config.Production).CreateDocumentPDF("Demo.Loan.FindRateProduction",1,"C:\Temp\Rate.pdf",.Log)
```

The PDF format requires that you have a PDF renderer installed; if you have configured one for Zen, then it becomes the default renderer. It also requires Java. See “Configuring Zen Reports for PDF Output” in *Using Zen Reports* for details.

2.9 Deleting a Production

To delete a production:

1. Navigate to the **Production List** page (**Ensemble > List > Productions**).
2. Click the production that you want to delete.
3. Click **Delete**.
4. Click **OK**.

2.10 Using the Production List

On the **Production List** page (**Ensemble > List > Productions**), you can use the following options:

- Click **New** to start the **Production Wizard** to create a new production in this namespace.
- Click **Open** to display the **Production Configuration** page for the selected production.

- Click **Export** to export the selected production. See [Deploying a Production](#) in *Developing Ensemble Productions* for details on exporting and deploying a production.
- Click **Delete** to delete the selected production.
- Click **Document** to view or generate configuration documentation for this production.
- Enter text in the **Search** text box to search for productions that contain the specified text in their definitions.

The table on this page provides the following information for each production:

- **Production Name** — The name of the production.
- **Status** — The status of the production.

If a production is [Suspended](#) or [Troubled](#), see “[Correcting Production Problem States](#)” in *Monitoring Ensemble*.

- **Last Start Time** — The date and time when the production was last started.
- **Last Stop Time** — The date and time when the production was last stopped.

3

Adding Business Hosts

This chapter describes how to use the **Production Configuration** page to add business hosts to a production. It contains the following sections:

- [Introduction](#)
- [Configuration Names](#)
- [Adding Business Hosts to a Production](#)
- [Wizard Options](#)
- [Enabling or Disabling a Business Host](#)
- [Changing the Class That a Business Host Uses](#)
- [Copying a Business Host](#)
- [Deleting a Business Host](#)
- [Repairing an Error](#)
- [Viewing and Configuring Connections](#)
- [Working with Multiple Versions of a Business Host](#)

For information on the [color coding](#) in the diagram, see the [previous chapter](#).

The next chapter describes how to [configure settings](#) for the production and all business hosts.

3.1 Introduction

An Ensemble business host is any business service, business process, or business operation within an Ensemble production. These are also referred to generically as *configuration items*.

A configuration item is always associated with a specific production. It may resemble or duplicate items in other productions. Each production is an entirely closed universe that does not use configuration items from other productions.

3.2 Configuration Names

By default, the *name* of a configuration item is the name of its underlying host class. However, you can assign a different name, to describe the purpose of the item, for example.

For example, if you have a business service class that communicates with a specific type of server, and you use it to communicate with the same *type* of server in different enterprise *locations*, you must configure the business service with different settings to communicate with each enterprise location, even though the type of server is the same. Each different configuration of the business service must have a different *Name* in the diagram (except see “[Working with Multiple Versions of a Business Host](#),” later in this chapter).

The following rules govern configuration names:

- The name must consist of at least one character.
- The name can contain letters, numbers, and any printable character except for the following: | ; , : [
- Neither the first nor the last character can be any of the following: ! \$.
- The name (if is it one character long) cannot be *

Important: You cannot change the name of an existing configuration item. If you require a name change, you can [copy](#) the item and [delete](#) the original item.

3.3 Adding Business Hosts to a Production

To add a business host to a production:

1. Identify (or create and compile) the appropriate business host class.
2. Open the production on the **Production Configuration** page.
3. Click plus-sign icon next to the **Services**, **Processes**, or **Operations** column heading.
4. Use the wizard that Ensemble displays. See the [next topic](#) for details on the options.
5. Click **OK** to add the process to the production.
6. Configure the business process as needed.

This process does not generate any new classes. It updates the production class.

3.4 Wizard Options

This section describes the options in the [Business Service Wizard](#), the [Business Process Wizard](#), and [Business Operation Wizard](#).

3.5 Options in the Business Service Wizard

The Business Service Wizard provides multiple tabs, which correspond to different types of business service classes to use. Click a tab and then specify values as follows:

- If you click the **All Services** tab, specify the following values:
 - Choose a host class from the **Service Class** list. If the class you need is not listed, create and compile the class in Studio, and then return here to choose it.
 - Specify a configuration **Service Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
 - Enter a text label in the **Display Category** field to sort and organize items within the production. **Display Category** names are case-sensitive, and space characters are allowed. To place an item in multiple categories, list them in the **Display Category** field separated by commas (do not allow spaces around these commas).
 - **Comment** is an optional text description.
- If you click the **HL7 Input** tab, specify the following values:
 - Choose **TCP**, **File**, **FTP**, **HTTP**, or **SOAP** to select an existing specialized Ensemble host class.
 - Specify a configuration **Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
 - Use the **Target Name** field to identify the business process or business operation to which this business service will send the HL7 messages that it receives.
- If you click the **X12 Input** tab, specify the following values:
 - Choose **TCP**, **File**, or **FTP** to select an existing specialized Ensemble host class.
 - Specify a configuration **Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
 - Use the **Target Name** field to identify the business process or business operation to which this business service will send the HL7 messages that it receives.
- If you click the **Business Metric** tab, specify the following values:
 - Choose a host class from the **MetricClass** drop-down list. If the class you need does not appear on this list, create the class in Studio, then return to choose it.
See “[Creating Business Metrics](#)” in *Developing Ensemble Productions*.
 - Specify a configuration **Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
 - Enter a text label in the **Category** field to sort and organize items within the production. **Category** names are case-sensitive, and space characters are allowed. To place an item in multiple categories, list them in the **Category** field separated by commas (do not allow spaces around these commas).
 - **Comment** is an optional text description.
 - **Call Interval** determines how often the business metric will recalculate the values of its properties. The **Call Interval** is in seconds, starting from a minimum of 0.1 seconds. The default is 5 seconds.

3.6 Options in the Business Process Wizard

The Business Process Wizard provides multiple tabs, which correspond to different types of business process classes to use. Click a tab and then specify values as follows:

- If you click the **All Processes** tab, specify the following values:
 - **Business Process Class** — Choose a base class from the list of valid business process classes. If the class you need does not appear on this list, create and compile the class and then return here to choose it.
 - Specify a configuration **Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
The wizard defaults to the business process class name if you leave this blank.
 - Specify other values as given after this list.
- If you click the **HL7 Router** or **X12 Router** tab, specify the following values:
 - **Auto-create Rule** — Select this check box to create a rule definition name based on the business process class name.
 - **Routing Rule Name** — Use the field to identify the name of the routing rule set to which this business process sends the messages that it receives. Only appears if the previous check box is cleared.
Once you select a rule name, you can click the magnifying glass to open the Ensemble Rule Editor.
 - Specify a configuration **Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
The underlying business process class is either `EnsLib.HL7.MsgRouter.RoutingEngine` or `EnsLib.MsgRouter.VDocRoutingEngine` depending on which type of router you choose.
 - Specify other values as given after this list.
- If you click the **Component** tab, specify the following values:
 - **Component Class** — Choose a base class from the list of valid business process classes designated as components.
 - **Component Name** — Enter a configuration name for this item. For rules, see “[Configuration Names](#),” earlier in this chapter. The wizard defaults to the component class name if you leave this blank.
 - Specify other values as given after this list.

Note that all types of business process share the following optional fields:

- **Display Category** — Enter a text label in the field to sort and organize items within the production. Category names are case-sensitive and space characters are allowed. To place an item in multiple categories, enter a comma-separated list.
- **Comment** — Enter a brief comment about the business process to appear in the informational settings.
- **Enable Now** — Select this check box if you want this business process to begin processing messages immediately when the production runs; clear it for the process to be initially disabled.

3.7 Options in the Business Operation Wizard

The Business Operation Wizard provides multiple tabs, which correspond to different types of business operation classes to use. Click a tab and then specify values as follows:

- If you click the **All Operations** tab, specify the following values:
 - Choose a host class from the **Operation Class** list. If the class you need does not appear on this list, create the class in Studio, then return here to choose it.
 - Specify a configuration **Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
 - Enter a text label in the **Display Category** field to sort and organize items within the production. **Display Category** names are case-sensitive, and space characters are allowed. To place an item in multiple categories, list them in the **Display Category** field separated by commas (do not allow spaces around these commas).
 - **Comment** is an optional text description.
 - Specify other values as given after this list.
- If you click the **HL7 Output** tab, specify the following values:
 - Choose **TCP**, **File**, **FTP**, **HTTP**, or **SOAP** to determine the host class. Each class already exists and requires no programming. Simply choose one.
 - Specify a configuration **Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
 - Specify other values as given after this list.
- If you click the **X12 Output** tab, specify the following values:
 - Choose **TCP**, **File**, or **FTP** to determine the host class. Each class already exists and requires no programming. Simply choose one.
 - Give the item a configuration **X12 Operation Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
 - Specify other values as given after this list.
- If you click the **Workflow** tab, specify the following values:
 - Choose a host class from the **Operation Class** drop-down list. If the class you need does not appear on this list, create the class in Studio, then return here to choose it.
 - Give the item a configuration **Operation Name**. For rules, see “[Configuration Names](#),” earlier in this chapter.
 - Choose whether or not to auto-create a workflow role.
 - Specify other values as given after this list.

All types of business operation share the following optional fields:

- **Display Category** — Enter a text label in the field to sort and organize items within the production. Category names are case-sensitive and space characters are allowed. To place an item in multiple categories, enter a comma-separated list.
- **Comment** — Enter a brief comment about the business operation to appear in the informational settings.
- **Enable Now** — Select this check box if you want this business operation to begin processing messages immediately when the production runs; clear it for the operation to be initially disabled.

3.8 Enabling, Disabling, or Restarting a Business Host

To enable, disable, or restart a business host, do either of the following:

- Double-click a host item. Ensemble displays a dialog box that allows you to enable, disable, or restart the host item depending on the current state of the production and the host item:
 - If the production is running and the host item is enabled, the dialog box gives you the option to disable the host item, restart the host item, or to cancel the request.
 - If the production is not running and the host item is enabled, the dialog box gives you the option to disable the host item or to cancel the request.
 - If the host item is disabled, the dialog box gives you the option to enable the host item or cancel the request.
- Select or clear the **Enabled** setting (as appropriate) and then click **Apply**. To restart a host item, first disable it and then enable it.

Note: You cannot disable a business process with a pool size of 0. The management portal does not allow this action because disabling it would stop all business processes with a pool size of 0, which use the same shared actor queue. If you want to disable only a single business process, you must first set its pool size to 1 or more. After you apply the settings, you can disable it. If you do want to stop all business processes using the shared actor pool, select **Production Settings** and set the **Actor Pool Size** to 0.

3.9 Changing the Class That a Business Host Uses

To modify a business host so that it is based on a different class:

1. Display the **Production Configuration** page:
2. Click the business host in the diagram.
3. Click the **Actions** tab.
4. Click **Change Class**.
5. Select a new class.

3.10 Copying a Business Host

To create a copy of a business host within a given production:

1. Display the **Production Configuration** page:
2. Click the business host in the diagram.
3. Click the **Actions** tab.
4. Click **Copy**.
5. Click **Copy** to create a copy of the selected business host.

A dialog box prompts you to enter a configuration name.

6. Enter a unique name and click **OK**.

When first created, the copy has the same host class and settings as the original; only the name is different. Generally your next step is to configure the copy to make it unique. For example:

- If you have an incoming TCP *business service* that receives messages from a client application, and you want to receive messages from a similar application on a different application server, you can copy the first TCP service and configure the copy with the other server address.
- If you have a *business process* for one message routing interface, and you want a similar one but with alterations for another interface, you can copy the first routing process and configure the copy to route messages between different sets of business services and business operations.
- If you have an outgoing email *business operation* that alerts a user, but you want to alert another user at different times of day, you can copy the first outgoing email operation and configure the copy with the other email address.

The copy has no relationship to the original item; you can configure, enable, and disable each item independently.

Note: The **Copy** command works only within the same production. You cannot copy a business host from one production to another.

3.11 Deleting a Business Host

To delete a business host within a given production:

1. Display the **Production Configuration** page:
2. Click the business host in the diagram.
3. Click the **Actions** tab.
4. Click **Delete**.

This process removes this item from the production configuration. This action does not delete the business host class on which the business host is based.


3.12 Repairing an Error

If the class for a given business host is not available, the diagram displays the item with a red background. To fix the error:

1. Select the item.
2. Click the **Actions** tab.
3. Now either click **Delete** to remove the item or click **Change Class** to choose a class.

3.13 Viewing and Configuring Connections

When you click the status indicator of a business host, lines connect items as defined by the values in the **Target Config Names** setting or, in the case of a routing process, as defined by the associated **Business Rule Name**. The following figure shows an example:



You can assign a business service **Target Config Names** by clicking its status indicator and dragging the pointer to a business process or operation until you see its status indicator highlighted. When you do so, the **Production Configuration** page displays a dialog window requesting you to confirm the connection. If you confirm the connection, the page displays a *Settings applied* message and the item is added to the list in the **Target Config Names** setting.

3.14 Working with Multiple Versions of a Business Host

During development, it can be convenient to include multiple “versions” of a business host in the production and then switch among them for testing.

Only one of them can be enabled at any time; when you enable one, Ensemble automatically disables any previously enabled version.

To create and work with multiple versions of a host:


1. Add the first business host as usual.
2. Add the next business host and provide the same configuration name as for the first one.

The production configuration still shows only one business host with the given name.


3. If you are not in listing view, click the listing view icon

4. Select the business host.

Now the diagram displays a small box that indicates the number of items that have this name, as follows:



Also, the area above the diagram shows a drop-down list that you can use to select the specific item to work with:



By default, the enabled version is selected. If no host is enabled, the selected version is the first business host that you added.

5. Use the **Item** list to select the version that you want to configure. Specify configuration details as usual and apply them.
6. Repeat if needed.

To understand why this is useful, consider the following: when testing or troubleshooting the production you might want to send messages by typing them at the console command line, or by reading data from files. But when running the production, you might intend for these messages to arrive from an external application via a TCP connection. Each means of obtaining input for the production requires a different business service host class.

4

Configuring Settings

This chapter describes how to configure settings. It contains the following topics:

- [Configuring Settings](#)
- [Understanding the Color Coding for Settings](#)
- [Searching for a Setting](#)
- [Getting Help for Settings](#)
- [Restoring a Setting to Its Default Value](#)

There are multiple ways to perform many tasks. This chapter describes only one procedure for any task.

4.1 Configuring Settings

To configure settings for a business host:

1. Click the business host.
2. Click the **Settings** tab.
3. Expand and collapse the groups as needed to see the settings. You can also [search](#) for a setting.
4. Edit values as needed.
 - Some configuration settings, take comma-separated lists to define their possible values. You can change these items either by editing the list directly or by selecting the check boxes of the desired values in the associated drop-down list. When you edit settings that use drop-down lists, be sure to click outside of the list to close it.
 - Some configuration settings have a magnifying glass icon next to them. You can click this to see more details of a selected value, or to open a new portal page for entering additional information. This depends on the type of setting you are editing.

See the reference “[Settings in All Productions](#)” at the end of this book. Also see other Ensemble books for information on specific adapters and business hosts.

5. Click **Apply**.

If the apply command is successful, you receive a *Settings applied* message.

Ensemble validates the values for settings. If you provide a string value for a setting that requires a numeric value, Ensemble does not apply that value.

Similarly, to configure settings for the production, first click **Production Settings**. This step returns the focus to the production and changes the options on the **Actions** tab. Then continue as described in the previous steps.

In both cases, the changes are immediately saved and take effect immediately.

4.2 Understanding the Color Coding for Settings

The setting names are color coded as follows:

| Color | Source |
|-------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Black | Setting value comes from the production definition — the value you enter and apply in the configuration page. |
| Green | Setting value comes from the class definition; it is the default value for the property as defined in the class. |
| Blue | Setting value comes from the default settings you enter in the Default Settings page for the namespace. See “ Defining System Default Settings ,” later in this book. |

4.3 Searching for a Setting

To find a setting more easily, use the **Search** option. Enter text to show all settings whose name, type, category, or value contains the search string. Click the X icon to clear the contents of the **Search** box.

4.4 Getting Help for Settings


This page provides context-sensitive help. Hover the cursor over any setting name to display its help text as it appears in the *Class Reference* for the associated class property or click the setting name to display the help text in a separate pop-up window.

The property name appears beneath the localized setting name in this window if the name is different.

Also see “[Settings in All Productions](#)” at the end of this book, as well as Ensemble books that discuss specific adapters and business hosts.

4.5 Restoring a Setting to Its Default Value

To restore a setting to its default value:

1. Click the default setting icon  on the **Settings** tab.

Ensemble then displays a dialog box with a table that displays the following columns:

| Column | Description |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Select check box | Shown only if the current value is not the default. |
| Setting | Name of the setting as displayed in the Management Portal. |
| Target | Indicates if the setting applies to a host or to an adapter. This is blank for a production setting. |
| Value | Current value of the setting. |
| Value Source | Source of the current value: <ul style="list-style-type: none"> <code>class definition</code> — the value is specified in the class on which this item is based. <code>default setting</code> — the value is a system default value. For details, see “Defining System Default Settings,” later in this book. <code>production definition</code> — the value is specified in the production definition. |
| Default | Default value for this setting. |
| Default Source | Source of the default value: <ul style="list-style-type: none"> <code>class definition</code> — if you see this, there is no system default for this setting. <code>default setting</code> <p>See the notes for Value Source.</p> |

- For each setting that you want to change, select the check box.
- Click **OK**. The property label changes color depending on the **Default Source**. See “[Understanding the Color Coding for Settings](#),” earlier in this chapter.

Or, if you make a mistake and want to return to the original values, click **Cancel**; the settings refresh to the previous values and the dialog box closes.

- Click **Apply** to save all your changes.

5

Configuring Alerts

This chapter describes how to configure a production to alert users about important events, such as events that require user intervention. It includes the following sections:

- [About Alerts](#)
- [Configuring an Alert Processor](#)
- [Configuring Alerts on Errors](#)
- [Configuring System Alerts on Queue Buildups](#)
- [Other System Alerts](#)

5.1 About Alerts

An *alert* sends notifications to applicable users while an Ensemble production is running, in the event that an alert event occurs. The intention is to alert a system administrator or service technician to the presence of a problem. Alerts may be delivered via email, text pager, or another mechanism.

The Ensemble alert mechanism works as follows:

- As part of the development process:
 - Within business host classes for the production, the developers include code that generates alerts when applicable. For information, see “[Generating Alerts](#)” in the chapter “[Programming in Ensemble](#)” in *Developing Ensemble Productions*.
 - The developers define an additional business host class called an *alert processor* (also called an *alert target*). The alert processor contains the logic to contact each user in the most appropriate way. The developers might also develop business operations for the alert processor to call. For information, see “[Defining Alert Processors](#)” in *Developing Ensemble Productions*.
- You configure the production to include the alert processor, along with any business services that it requires. For details, see the [next section](#).

All alerts *also* write messages to the Ensemble [Event Log](#), with the type Alert. See [Monitoring Ensemble](#) for details.

5.2 Configuring an Alert Processor

Each time any alert is sent, the alert text is added to the Ensemble Event Log. This mechanism might be too passive for the most urgent messages. If you want the production to also actively seek the user, you must define and configure a business host that has the ability to contact a user device. This business host is known as an *alert processor* or an *alert target*.

To add the alert processor to the production:

1. Add the business host class to the production. This class is a business operation or business process class, depending on its implementation.
2. For the configuration name, specify `Ens.Alert`
3. If the alert processor has settings such as email addresses and telephone numbers, configure those.
4. Add any business services that the alert processor calls.

Note: Any production can include no more than one alert processor.

5.3 Configuring Alerts on Errors

Ensemble can send alerts automatically whenever a business host encounters an error condition. The [Alert On Error](#) setting controls this behavior. If [Alert On Error](#) is True, then whenever the business host encounters an error, Ensemble triggers an alert.

Note that business hosts provide an optional grace period that enables the business host to retry before triggering the alert. Depending on the kind of business host, this grace period is specified by the setting [Alert Grace Period](#) or [Alert Retry Grace Period](#).

For details on these settings, see “[Settings in All Productions](#).”

5.4 Configuring Alerts on Queue Buildups

Ensemble can send alerts when a business host’s queue has too many messages or has messages that have waited too long. To enable these alerts, specify the following settings with nonzero values:

- [Queue Count Alert](#) — Minimum number of items in the queue needed to trigger an alert. This alert has the prefix `QueueCountAlert:` (not localized). This alert is useful in situations where large queues are building up.
- [Queue Wait Alert](#) — Minimum length of time for a message to wait in a queue to trigger an alert. This alert has the prefix `QueueWaitAlert:` (not localized). This alert is useful in situations where a queue is not processing messages.

For details, see “[Settings in All Productions](#).”

5.5 Other System Alerts

Ensemble generates alerts on other occasions, including the following:

- When a job is marked as dead.

This alert is prefixed with the non-localized text: `DeadJobAlert` : for simplified routing and handling.

- When a business host is marked as inactive, according to its [Inactivity Timeout](#) setting. For details, see “[Settings in All Productions](#).”
- When a business operation suspends its current message.

6

Defining Reusable Items for Use in Settings

This chapter describes how to define certain reusable items for use as values of settings. It contains the following topics:

- [Defining Business Partners](#)
- [Defining Credentials](#)
- [Defining Schedule Specifications](#)

You might also need to define SSL/TLS configurations. For information, see “Using SSL/TLS with Caché” in the *Caché Security Administration Guide*.

Also see “[Defining System Default Settings](#)” in the next chapter.

6.1 Defining Business Partners

Ensemble provides a way to add additional information to an Ensemble production to help with the management of a production. A business partner profile is information about an organization or application connected to your Ensemble system. For each business partner, you can provide information such as the partner name, notes, primary and alternative contacts, and contact details. Defining a profile has no effect on the behavior or running of the production. It simply gives you a means to store more information.

For example, suppose your production talks to ABC Hospital and XYZ Hospital. You can enter profiles for both of these along with contact information. When you configure items that talk to these organizations, you can specify the defined **Partner Name** for each business host.

The **Business Partner Viewer** page (**Ensemble > Configure > Business Partners**) allows you to view and edit profiles to store information about your business partners for use in your productions.

The page lists any Business Partner Profiles you have already defined and allows you to enter a new profile or edit an existing one in the right pane of the page.

Enter the required unique **Partner Name** and optional **Description** and then the following information for a **Primary Contact** and **Alternate Contact**:

- **Name**
- **Title**

- **Email address**
- **Phone Number**
- **Mobile Phone Number**
- **Notes**

Click **Save** to store this information in the current namespace. When you are configuring productions, this name appears in the **Business Partner** configuration setting list, which you can choose to use in your production enabling you to categorize business host items in your production by business partner.

To delete a specific business partner profile, select it from the list so it appears in the right pane and then click **Remove**.

6.2 Defining Credentials

Some remote systems require a username and password to log into that system. A username-password pair is a login credential. Ensemble permits you to store login credentials in a centralized, secure table; only users with appropriate access to the Management Portal can view and edit this table.

The **Credentials Viewer** page (**Ensemble > Configure > Credentials**) displays the Credentials table for the current namespace.

Each entry in the Credentials table has an **ID** which you use as the value of the **Credentials** setting when configuring business services or business operations for the production. Adding an entry to the Credentials table for a production consists of assigning an **ID** to a username-password pair. You can also store an informational business partner name with the credential.

The **Credentials** page displays a list of defined credentials associated with the current namespace. Each row in the table has the following columns:

- **ID** — Unique string that identifies this username-password pair; the name you use in the **Credentials** setting when configuring a business service or business operation to establish a remote connection.
- **User name** — Username with which to log on to the remote system.
- **Password** — Password corresponding to the logon username.
- **Business Partner** (*Optional*) — Name of the [business partner](#) profile associated with this item.

When editing, you can choose a profile from the list and view its details by clicking the magnifying glass. You can also create or edit a profile by clicking the **Business Partners Configuration Page** link.

When you select a Credential row, the right pane displays the current settings. If you do not select a row, the right pane shows empty fields for you to create a new credential. Enter values in the fields as outlined in the table description. You have the choice of two actions to perform in the **Credentials Viewer**:

- Click **Save** to store the updated or new values as a credential and display it in the table.
If you choose to edit a row and change the ID, when you click **Save**, you must verify that you want to rename the credential.
- Click **Remove** to delete the selected credential.

CAUTION: You cannot undo the **Remove** operation.

6.3 Defining Schedule Specifications

The default scheduling for business hosts is for them to run whenever the production is running. However, a finer control is possible. Not only can you enable and disable business hosts, but the **Production Configuration** page also provides a **Schedule** setting for each business host. This is an optional command string that schedules the item to be stopped and started at specific times and on specific days of the week, month, or year. When it is time to start, if the item is enabled, the scheduler starts it; when it is time to stop, if the item is running, the scheduler stops it.

The **Schedule Spec Editor** page (**Ensemble > Configure > Schedule Specs**) aids you in creating a string to use in this configuration setting. Once you create a schedule string and give it a name, you can use this string as a value for the [Schedule](#) configuration setting.

6.3.1 Schedule Specifications

The **Schedule** string is a comma-separated list of event specifications. Each event specification has the following format:

action : *YYYY-MM-DDThh:mm:ss*

Where each item in the event specification, from left to right, has the described values:

| Item | Possible Values |
|-------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>action</i> | START or STOP indicates the desired action |
| : | Required separator |
| <i>YYYY-MM-DD</i> | <p>Either:</p> <ul style="list-style-type: none"> • <i>YYYY</i> is the year as 4 numerals • <i>MM</i> is the month as 2 numerals • <i>DD</i> is the day of the month as 2 numerals • Any of these fields may be the single character * (asterisk) indicating all years, all months, or all days <p>Or:</p> <ul style="list-style-type: none"> • <i>YYYY</i> is the word WEEK • <i>MM</i> is the specific occurrence of the day of the week (indicated by <i>DD</i>) in the month (01 = first occurrence of the specific day of the week in the month, 02 = second occurrence in the month, etc.) • <i>DD</i> is a specific day of the week (00 = Sunday, 01 = Monday, etc.) • <i>MM</i> may be * for all occurrences and <i>DD</i> may be * for all days <p>Once a field is specified as *, all fields to the left of it are also assumed to be *. Thus, if the <i>DD</i> value is *, the <i>MM</i> value is treated as * even if it has a specific numeric value. Similarly, if <i>MM</i> is *, <i>YYYY</i> is treated as *.</p> |
| T | Required separator |
| <i>hh:mm:ss</i> | Hour, minute, and second |
| , | Use the comma separator only if there is another event specification after the current one. Do not use it at the end of the Schedule string. |

If you set a schedule specification to be deployable, then the specification can be included when you export the production. When you are exporting the production, select **Deployable Settings** and select the `Ens.Util.Schedule` setting.

See the `Ens.ScheduleHandler` entry in the *Class Reference* for more information.

The following sections provide [examples](#), details on [Daylight Saving Time](#) considerations, and the [intended use and limitations](#) of the setting.

6.3.2 Examples

If your schedule contains recurring events, the **Schedule** setting requires both **START** and **STOP** actions. If your schedule setting is an absolute one time event, then you need only use the appropriate single **START** or **STOP** action. In most cases, **Schedule** strings should contain both a **START** and a **STOP** action.

Some examples of **Schedule** strings follow:

- Start the business host every day at 8 a.m. and stop it every day at 5 p.m.
`START:*-*-*T08:00:00,STOP:*-*-*T17:00:00`
- Stop every year on January 2 at 7 a.m. and start again on January 3 at 7 a.m.
`STOP:*-01-02T07:00:00,START:*-01-03T07:00:00`
- Start every month on the second day of the month at 8 a.m. and stop every month on the tenth day of the month at 8:30 p.m.
`START:*-*--02T08:00:00,STOP:*-*--10T20:30:00`
- Stop every Sunday at 10 a.m. and start every Monday at 8:30 a.m.
`STOP:WEEK-*--00T10:00:00,START:WEEK-*--01T08:30:00`
- Start every third Tuesday at 9 a.m. and stop every third Friday at 4 p.m.
`START:WEEK-03-02T09:00:00,STOP:WEEK-03-05T16:00:00`
- Stop on December 31, 2010 just before midnight.
`STOP:2010-12-31T23:59:59`
- Start on January 3, 2011 at 6:45 a.m.
`START:2011-01-03T06:45:00`
- The following two strings are equivalent: Start every day at 2 a.m.
`START:*-*-*T02:00:00`
`START:WEEK-*-*T02:00:00`

6.3.3 Scheduling and Daylight Saving Time

When daylight saving time (DST) begins, clocks skip an hour that day, usually from 2:00 a.m. to 3:00 a.m. Any item you have scheduled that falls into that nonexistent hour takes place at the beginning (which is also the end) of that hour. For example, on the day DST begins, an event scheduled to take place at 2:15 a.m. takes place at 2:00 a.m. (which is also 3:00 a.m.).

When DST ends, an hour of the day repeats, usually from 1:00 a.m. to 2:00 a.m. Any item you have scheduled that falls in that repeated hour takes place only once. Whether the event takes place on the first occurrence of the scheduled time or the second occurrence in the repeated hour depends on the operating system, but it only takes place once. For example, on a

Windows system on the day DST ends, an event scheduled to take place at 1:15 a.m. takes place at the second occurrence of 1:15 a.m.

6.3.4 Intended Use and Limitations

The **Schedule** setting starts and stops production business hosts according to a schedule; it is not a task scheduler. The schedule string defines a square wave in time declaring during what time intervals the item *should* be running, in between which it should be not be running. Ensemble cannot prevent scheduled transitions from being interrupted or superseded by other production events.

The scheduler wakes up periodically (it sets its own alarm clock for when any scheduled item next expects a transition) and attempts to start or stop any items that are not currently in the expected state according to their schedule strings. It runs the **UpdateProduction()** method of the `Ens.ScheduleHandler` class and checks what event it needs to schedule next.

There are two general classes of things that can prevent transitions from taking place as the schedule string indicates:

- The scheduler might be unable to cause the intended state change; that is, the **UpdateProduction()** method fails to affect the relevant items.

For example, an item could be in a Read timeout or some other busy state that lasts longer than the Update timeout. Another example is a business host the scheduler starts cannot be stopped by the scheduler if the item is in the middle of a synchronous call. The business host must wait for a response to the call before the scheduler stops it.
- The scheduler might not be able to wake up at the intended time. Examples of conditions that could cause this: the CPU is busy, a queue builds up of the alarm clock messages for the scheduler, the scheduler is itself disabled or crashed, the production is down, etc. The scheduler is not guaranteed to wake up during any particular interval, and when it does wake up it only looks at the intended state for the current moment, not at any history of when it *should have* woken up.

Use of the schedule setting is not intended or designed as an event signaling device. It is intended to accommodate planned outages and scheduled intervals of activity or inactivity. If you have events that you must trigger at a particular time or as soon as possible thereafter, Ensemble provides better alternatives:

- You can configure your business service to use an inbound adapter with the implemented **OnTask()** method where you call the business service. Ensemble provides classes for many types of inbound adapters. See the `Ens.InboundAdapter` entry in the *Class Reference* and the books in the *Ensemble Adapter Guides* set for details.
- If you do not want to use an adapter, you can call the business service programmatically and schedule it to run using the **Task Scheduler Wizard** page (`/csp/sys/op/UtilSysTaskHome.csp`) in the Management Portal. To access the **Task Scheduler Wizard** page, select **System Operation > Task Manager > New Task**. This gives you finer control in situations such as the system being down at 1:00 a.m.

The recommended approach is to configure the business service with **Pool Size** = 0 and then use the Task Manager to launch a task that calls **CreateBusinessService()** on it and invokes **ProcessInput()** on the resulting service instance object. The advantage of calling a business service this way is that you call it at the time you want and it runs only once. If Ensemble happens to be down at that time, your task can register an error. See the following sections for details:

- “Using the Task Manager” in the chapter “Managing Caché” in *Caché System Administration Guide*
- “[Invoking a Business Service Directly](#)” in *Developing Ensemble Productions*

7

Defining Other Options for Ensemble

This chapter describes other options that you can define or configure for an Ensemble namespace. The following topics describe these settings:

- [Defining Data Lookup Tables](#)
- [Defining System Default Settings](#)
- [Configuring Source Control Settings](#)

Also see “[Configuring the Message Bank Link](#),” later in this book.

7.1 Defining Data Lookup Tables

The Lookup Tables portal page allows you to create and configure data tables to support the Lookup and Exists utility functions. The Lookup utility function is provided so that you can easily perform a table lookup from a business rule or DTL data transformation.

For details, see “[Ensemble Utility Functions](#)” in *Developing Business Rules*.

The Lookup function works only after you have created a lookup table and have populated it with data. You can do this selecting **Ensemble**, **Configure**, and **Data Lookup Tables**. If you click **Open**, a dialog box lists the lookup tables that are defined in the namespace. Select a lookup table and Ensemble displays the following form:

| Key | Value | Original Value |
|--------------------------|---------------------|----------------|
| ✗ ABC_HL7FileService | temp_1@company.test | |
| ✗ BadMessageHandler | temp_3@home.test | |
| ✗ Extra_Observations | temp_5@company.test | |
| ✗ MsgRouter | temp_3@home.test | |
| ✗ Priority_FileOperation | temp_5@home.test | |
| ✗ Regular_FileOperation | temp_4@company.test | |
| ✗ XYZ_HL7FileService | temp_2@company.test | |

To edit entries in a lookup table, you can:

- Delete an entry by selecting the red X icon. The entry is deleted when you save the table. Until you have saved the table, you can restore the entry by selecting the green + icon that is displayed to the left of the entry.

- Update an entry by entering the same key as the entry and a new value in the form on the right and then selecting **Apply**. After you update the value, the original value is displayed in the **Original Value** column until you save the lookup table. Selecting an existing entry populates the form on the right with the entry's current values.
- Add a new entry by entering a new key and its value in the form on the right and selecting **Apply**.
- Undo the previous action by selecting the curved arrow in the menu bar.

Note: Selecting an entry has only one effect: initializing the values in the form on the right. Selecting **Apply** acts on the entry specified in the **Key** field not on the selected entry. If the key field matches an existing entry, that entry is updated. If the key field does not match an existing entry, then a new entry is added. Selecting the green + icon on the menu bar or selecting **Discard** clears the form but does not have any other effect.

You can take an action by selecting one of the following buttons:

- **New**—Displays a form so that you can name the lookup table and then displays the empty table. Add entries to the table by entering in key and value pairs and selecting **Apply** for each pair. You must select **Save** to make the lookup table permanent.
- **Open**—Displays the lookup tables defined in the current namespace and allows you to select one.
- **Save**—Saves the current lookup table with any edits that you have applied. Clears the **Original Value** column and removes deleted records.
- **Save As**—Saves the current table entries to a new table. Specify the new table name and select **OK**. Clears the **Original Value** column and removes deleted records.
- **Delete**—Deletes the current table. If you have made any edits to the table since opening it, Ensemble asks if you want to leave the page. To delete the table, select **Leave Page**. If you select **Stay on Page**, Ensemble treats the current table as if it were a new table.
- There are two ways to import lookup tables: **Import Legacy** and **Import**. An important difference between them is that when you are importing a lookup table with the same name as an existing lookup table, **Import Legacy** merges the existing table with the data from the file and **Import** replaces the existing lookup table with the data from the file.
 - **Import Legacy**—Imports the lookup tables defined in the file. If an imported lookup table has the same name as an existing table, the values are merged. If a key is defined in the file, it overwrites any existing value of that key in the lookup table.
 - **Import**—Adds new lookup tables that are defined in an XML file. If any of the new tables have the same name as an existing table, the new table replaces the old one. Select **Browse** to specify an XML file, then select **Open**. The form displays the LookUp Table (LUT) document or documents defined in the file. You can select all of the lookup tables or some of the lookup tables listed, then select **Import** to import the lookup table(s). The **Import** button can only import the new file format (see following note).

Note: There are two lookup table file formats: a new format and the legacy format. The new format contains additional XML Document tags. **Import Legacy** can handle both the new and the legacy format, but **Import** can only handle the new format. The new format is exported by Studio and by the **Export** portal button. The old format is exported by the **Ens.Util.LookupTable.%Export()** method. See [Lookup Table File Format](#) for a description of the lookup table file formats.

- **Export**—Exports the current table to an XML file. Although you can specify the name of the file, the lookup table exported has the same name as the current lookup table and does not use the file name. You can export only using the current XML format; you cannot export the legacy XML format with this release.

CAUTION: You cannot undo the **Delete**, **Import**, or **Import Legacy** operation.

Note: If there is an existing lookup table with the same name, the **Import** button has a different behavior from the **Import Legacy** button. The **Import** button completely replaces the contents of the existing lookup table. In contrast, the **Import Legacy** button merges the new values with the existing values.

For information on working with lookup tables in programs, see “[Programmatically Working with Lookup Tables](#)” in *Developing Ensemble Productions*.

The following subsections describe:

- [Lookup Table File Format](#)
- [Importing Flat Files As Data Lookup Tables](#)

7.1.1 Lookup Table File Format

There are two XML formats that describe lookup tables: the new format and the legacy format.

The new Lookup Table XML format consists of one or more XML Document elements, for example:

```
<?xml version="1.0" encoding="UTF-8"?>
<Export generator="Cache" version="25" zv="Cache for Windows (x86-64) 2015.1 (Build 378U)"
  ts="2014-10-21 11:52:51">
  <Document name="AlertTable.LUT">
    <lookupTable>
      <entry table="AlertTable" key="ABC_HL7FileService">temp_1@company.test</entry>
      <entry table="AlertTable" key="BadMessageHandler">temp_1@company.test</entry>
      <entry table="AlertTable" key="Extra_Observations">temp_5@company.test</entry>
      <entry table="AlertTable" key="MsgRouter">temp_3@home.test</entry>
      <entry table="AlertTable" key="Priority_FileOperation">temp_5@home.test</entry>
      <entry table="AlertTable" key="Regular_FileOperation">temp_4@company.test</entry>
      <entry table="AlertTable" key="XYZ_HL7FileService">temp_2@company.test</entry>
    </lookupTable>
  </Document>
</Export>
```

The XML elements have the following syntax:

- Each Document element must have a name attribute that specifies the lookup table name and has a file type .LUT.
- Each Document element contains one lookupTable element.
- Each lookupTable element contains a list of entry elements.
- Each entry element has a table attribute that specifies the same table name as specified in the Document name, specifies a key attribute, and specifies the value of the entry as text.

The legacy format exported by the **Ens.Util.LookupTable.%Export()** method and the portal in Ensemble 2014.1 and earlier versions does not have the Document element. It consists of just a single lookupTable element and the entry elements that it contains. It can contain entries for multiple lookup tables by specifying different names in the table element.

7.1.2 Importing Flat Files as Data Lookup Tables

You can import a flat file as a data lookup table, if the file is as follows:

- It can include a header row.
- It must include three values, separated by spaces, commas, tabs, or another delimiter.
- From left to right, the three values must correspond to the **Value** column of a lookup table, the **Key** value of a lookup table, and the desired name of the lookup table.

To import such a file as a lookup table, use the Data Import Wizard, as described in “Importing Data from a Text File” in *Using Caché SQL*. For the schema name, use **Ens_Util**. For the table name, use **LookupTable**.

7.2 Defining System Default Settings

This section discusses system default settings. It includes the following sections:

- [Purpose of System Default Settings](#)
- [Accessing the System Default Settings](#)
- [Creating or Editing a System Default Setting](#)

7.2.1 Purpose of System Default Settings

The purpose of *system default settings* is to simplify the process of copying a production definition from one environment to another. In any production, the values of some settings are determined as part of the production design; these settings should usually be the same in all environments. Other settings, however, must be adjusted to the environment; these settings include file paths, port numbers, and so on.

System default settings should specify only the values that are specific to the environment where Ensemble is installed. In contrast, the production definition should specify the values for settings that should be the same in all environments.

To find the value for a setting for a production, business host, or adapter, Ensemble searches the following locations, in order:

1. The production definition. If Ensemble finds a value for a setting here (even if the value is an empty string), it uses that value.
2. The system default settings, which are stored outside the production definition.
If Ensemble finds a value here (even if the value is an empty string), it uses that value.
3. The value of the setting as specified in the definition of the class on which the production, business host, or adapter is based.

Ensemble uses this value only if there is no system default for the setting.

Some settings do not have any default value.

Note: The PoolSize setting cannot be included in the system default settings. This setting is always controlled by the production.

When you configure a production, the labels are color-coded to indicate whether the value was set in the production, the system default settings, or the class definition. See “[Understanding the Color Coding for Settings](#)” for more information.

7.2.2 Accessing the System Default Settings

To access the System Default Settings page, select **Ensemble**, **Configure**, and **System Default Settings**. The System Default Settings page displays the settings defined in the namespace:

New
Edit
Delete

System Default Settings

System Default Settings currently defined in namespace ENSDEMO:

| Production Name | Item Name | Host Class Name | Setting Name | Setting Value | Deployable |
|-----------------|-----------|-----------------|-----------------|---------------|------------|
| * | * | * | ShutdownTimeout | 180 | No |

To create a new system default setting, click **New**. To edit an existing setting, select the setting and click **Edit**. To delete a setting, select the setting and click **Delete**.

The following elements define a system default setting:

- **Production Name**—Optionally, specifies the production to which this default applies. If set to *, this default applies to all productions in the namespace.
- Note:** You cannot change the value of this field once you save the default. You must delete the default and create a new one.
- **Item Name**—Optional, specifies the business host to which this default applies. If set to *, this default applies to all hosts in the production or in all productions.
- **Host Class Name**—Optional, specifies the class of the business host to which this default applies. If set to *, this default applies to all hosts in the production or in all productions.
- **Setting Name**—Specifies the name of the property to set. Note that property names do not include spaces. In most cases, the property name is similar to the setting name, with the spaces removed. For example, the setting **Log Trace Events** is based on a property called LogTraceEvents.

Tip: You can see the property name within the popup window that displays descriptive text for the setting.

- **Setting Value**—Specifies the value to assign to the property. If this field is blank; it sets the default to an empty string.
- **Description**—Optional, specifies a description of the default.
- **Deployable**—If set, the system default setting can be deployed.

7.2.3 Creating or Editing a System Default Setting

If you are creating a new system default setting or editing an existing one, Ensemble displays the following form:

Save
Cancel
Reset
Expand Tree
Contract Tree

Use the form below to edit a System Default Setting in namespace ENSDEMO:

Production

 Required. Use * to match all.

Item Name

 Required. Use * to match all.

Host Class Name

 Required. Use * to match all.

Setting Name

 Required.

Setting Value

Description

Deployable
☐

Some of the fields above can be filled in by dragging and dropping from the corresponding elements in the right panel.

The tree below contains all Productions that cur

Productions

- + Demo.ComplexMap.SemesterPro
- + Demo.DICOM.Production.Modalit
- + Demo.DICOM.Production.Router
- + Demo.DICOM.Production.Storage
- + Demo.DICOM.Production.Storage
- + Demo.DICOM.Production.Storage
- + Demo.DICOM.Production.WorkLis
- + Demo.Dashboard.Production
- + Demo.FloodMonitor.Production
- + Demo.HL7.MsgRouter.Production
- + Demo.HL7v3.Production.Interface
- + Demo.Loan.BankUSProduction
- + Demo.Loan.FindRateProduction
- + Demo.REST.Production
- + Demo.RecordMap.Production
- + Demo.SAP.Production.BootStrap
- + Demo.SAP.Production.Minimal
- + Demo.Workflow.Production
- + Demo.X12.BatchSortProduction
- + Demo.ZenService.Prod.GetTheW

Other User Host Classes

Host Classes From Ensemble Libran

The System Default Setting page allows you to create a new system default setting or edit an existing one. For convenience it displays a tree of productions and other classes. This allows you to find existing settings and drag the names and values to the form. The **Expand Tree** and **Contract Tree** buttons and the plus and minus icons allow you to explore the tree to locate the property you are seeking.

When you have completed defining or updating the system default setting, click **Save**. The **Cancel** button discards any changes and returns to the list of system default settings without creating or updating a setting. The **Restore** button returns to fields to their initial values and allows you to edit the values.

7.3 Configuring Source Control Settings

Ensemble contains a template, `EnsPortal.Template.devPage`, to implement a browser-based interface to existing source control hooks. There is a flag to indicate whether the source control system requires a project context to be supplied to work correctly. The flag is activated as follows:

```
Set ^%SYS("Ensemble","SourceControl", $namespace, "ProjectContext") = 1
```

Existing user templates used as dialog windows in Studio must include the `Ens_SourceControl.js` in `/csp/broker/ensemble/` (which can be referenced by the path `ensemble/Ens_SourceControl.js`) to manage your browser-based interactions. This inclusion is required both for CSP pages and Zen pages. Depending on the context required by your source control hooks, you may need to add some extra data to certain returns.

You can configure source control settings for each Ensemble namespace. For information on this, see the “Using Studio Source Control Hooks” appendix in *Using Studio*. Also see the Source Control Settings entry in the *Caché Additional Configuration Settings Reference*.

8

Configuring the Enterprise Message Bank

The Enterprise Message Bank is an optional remote archiving facility where you can collect messages, Event Log items, and search table entries from *multiple* Ensemble client productions.

This chapter describes how to configure it. It discusses the following topics:

- [Configuring the Message Bank Link](#)
- [Configuring a Client Production to Send Messages](#)
- [Configuring the Message Bank Service on the Server](#)

The following chapter [Identifying Enterprise Systems for Viewing and Monitoring](#), describes how to configure enterprise systems so that you can resend messages from the Message Bank.

For information on defining the Enterprise Message Bank, which is a specialized Ensemble production, see “[Defining an Enterprise Message Bank](#)” in *Developing Ensemble Productions*.

For information on using it, see “[Using the Enterprise Message Bank](#)” in *Monitoring Ensemble*.

8.1 Configuring the Message Bank Link

The **Configure Message Bank Link** page (**Ensemble > Configure > Message Bank List**) allows you to configure a link (for this namespace) to the Enterprise Message Bank.

On this page, provide the following information so the Ensemble can connect to the Message Bank (if defined):

- **Web Server IP Address** — Specify the IP address of the machine on which the Message Bank is running.
- **Web Server Port Number** — Specify the port number used by the web server that is serving Ensemble on that machine.
- **Instance Prefix** — Specify the path for the instance of Ensemble on the web server. Typically, this is not needed on development systems using the web server installed with Ensemble. However, this is required if you are using HealthShare Health Connect as the target Message Bank. If you have deployed Ensemble to provide its services through another web server, potentially with other instances of Ensemble using the same web server, you must specify this prefix so that the Message Bank can construct URLs that connect with the correct Ensemble instance through the web server.
- **Message Bank Production Namespace** — Specify the Caché namespace in which the Message Bank production is running.
- **Use SSL To Connect To The Message Bank Web Server** — Select this to use SSL/TLS to connect to the Message Bank.

For information on defining the Enterprise Message Bank, which is a specialized Ensemble production, see “[Defining an Enterprise Message Bank](#)” in *Developing Ensemble Productions*.

8.2 Configuring a Client Production to Send Messages

You must configure each desired client production to send messages to the Message Bank. For each client production, perform the following configuration steps:

1. Add the specialized message bank operation (Ens.Enterprise.MsgBankOperation) to the production and configure it as needed.

Note: For this business host, **Operation Name** must be the Message Bank operation class name. Either leave this blank to use the default class name or enter `Ens.Enterprise.MsgBankOperation`.

See the following subsection for [configuration](#) details.

2. If you have not yet done so, configure the link to the Message Bank, as described in the [previous section](#).

Or navigate to the **Configure Message Bank Link** page (**Ensemble > View > Enterprise Message Bank**). The first time you enter the **Enterprise Message Bank** page, Ensemble prompts you for information to define the link. This information is the same as described earlier.

Now the production is configured to send messages to the Message Bank, and the Management Portal has a link to the Message Bank web pages.

8.2.1 Configuring a Message Bank Business Operation

Configure the following settings specifically for the Message Bank:

Enable Archiving

Set to True. This starts messages queuing from all business hosts in the client production. Note that this queueing continues even if you disable the operation and while it is not able to connect to the Message Bank. The operation forwards any queued messages to the Message Bank server whenever it is enabled.

If set to False, the operation does not queue any messages for the Message Bank.

IP Address

IP address of the Message Bank production. Note that this does not include the web server port number.

Port

TCP port number used by the Message Bank production input service (9192 is the default).

Optionally configure the following additional settings:

Archive Items

Controls which messages to send to the Message Bank. The default behavior is to archive everything except scheduler messages as shown by the value:

```
*[ * ], -Ens.ScheduleService[ * ], -Ens.ScheduleHandler[ * ]
```

See the [following subsection](#).

Event Log Interval

How frequently should we check for conforming Event Log events that may need to be forwarded to the Message Bank server. 0 means check only when messages are being forwarded.

Force Keepalives

If set to True, send empty event submissions periodically if no conforming events need to be submitted.

For information on other settings, see the following:

- “[Settings in All Productions](#)” at the end of this book.
- “[Reference for Settings](#)” in *Using TCP Adapters with Ensemble*. (The `Ens.Enterprise.MsgBankOperation` class uses a TCP adapter and thus inherits settings from it.)

8.2.2 Details for the Archive Items Setting

The **Archive Items** setting controls which messages the production sends to the Message Bank. It is a comma-separated list of configuration names of items whose messages are to be archived to the Message Bank server.

Archive log events for each item using the following colon-separated syntax:

```
item[evtype1:evtype2:Trace_cat]
```

Within the event type brackets, you can use the following characters in your selection list:

| Pattern character | Placement | Resulting action |
|-------------------|--------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| * | | include all event types |
| – | at the front of an item | exclude the type from archiving entirely |
| ! | at the end of an item | exclude message bodies from archiving |
| \$ | at the end of an item | exclude search table entries from archiving |
| – | at the end of an item | exclude message headers from archiving |
| — | for events of type Trace | optionally used to select a particular category of trace event. Event type Trace without a suffix means Trace events of all categories. |

For example:

- `* [*]` — Archive everything
- `*$ [*] , Ens.Alert ! [- *]` — Archive all events, headers, and bodies but not SearchTable entries; but do not archive bodies or events from item `Ens.Alert`.

Note: Ensemble only archives trace events if it has logged them. You can use these settings only to restrict which *logged* events get archived, not to archive any events that you did not configure to be logged.

8.3 Configuring the Message Bank Service on the Server

The `Ens.Enterprise.MsgBank.TCPService` component on the Message Bank server helps process the incoming messages from the Message Bank client productions. If you have configured enterprise systems, the `TCPService` uses the information that you defined to associate the incoming message with the enterprise system. See “[Identifying Enterprise Systems for Viewing and Monitoring](#)” for details on configuring enterprise systems. If you do not identify the enterprise system, the monitor service identifies the incoming message based on the elements of the message.

There are two cases where it there may be conflicting information to identify the enterprise system sending the message:

1. If the enterprise system has multiple IP addresses and the system restarts it may be sending messages from a different IP address. To instruct the Message Bank to recognize that these messages are coming from the same enterprise system as the earlier messages, select the **Ignore Client IP Changes** check box on the `Ens.Enterprise.MsgBank.TCPService`.
2. Although it is not a recommended configuration, it is possible to terminate an enterprise system and restart a new one with the exact same configuration and name but resetting the message IDs. Since the message IDs are not related to the ones in the messages sent by the previous enterprise system, the Message Bank should treat it as a new enterprise system. In this case you should clear the **Ignore Client IP Changes** check box on the `Ens.Enterprise.MsgBank.TCPService`.

The **Ignore Client IP Changes** check box does not affect how the Message Bank treats enterprise systems that are part of a Caché mirror set (see “Mirroring Architecture and Planning” in the *Caché High Availability Guide*).

9

Identifying Enterprise Systems for Viewing and Monitoring

On systems with the Enterprise Message Bank, Enterprise Message Viewer, or Enterprise Monitor, you should identify the productions that you are monitoring or whose messages you are viewing. These productions are called Enterprise Systems. When you identify a production you specify its system address and the credentials needed to access it. To use the Enterprise Message Viewer or Enterprise Monitor for a production you must identify the production in the Enterprise System list. Although the Enterprise Message Bank can receive messages without having the sending production listed as an enterprise system, it cannot resend messages without access to the credentials. Although you can monitor messages on the Message Bank without configuring the enterprise systems, you should configure an enterprise system for every production sending messages to the Message Bank.

To enable access to the productions, do the following in the Management Portal on the Message Bank Server or on the system with the Enterprise Message Viewer:

1. Create Ensemble credentials that have a Caché username and password for a user that has sufficient privileges to access the production.

For information, see “[Defining Credentials](#).”

2. If needed, create an SSL configuration to connect to this client production.

For information, see “Using SSL/TLS with Caché” in the *Caché Security Administration Guide*.

3. Navigate to the **Enterprise Systems** page (select **Ensemble** > **Configure** > **Enterprise Systems** from the Home page). Ensemble then displays the list of systems that are currently defined.

View and edit participating enterprise client systems

[|<](#) [<<](#) [>>](#) [|>](#) Page 1 of 1 [New Connection](#)

| Client Systems | | | | | | |
|-------------------------------|---------|--------------------|--------------|------------------|-------------------|---------------------------------------------|
| Client Nickname | Node Id | Web IP Address | Namespace | SOAP Credentials | SSL Configuration | Threshold |
| HL7 | | jgoldman6420:57776 | ENSDemo | SASSY | | edit delete |
| Students with Complex Records | | localhost:57779 | ENSDemo | SASSY | | edit delete |
| mary | | sutton:57459 | ManagedAlert | SASSY | | edit delete |
| self | | jgoldman6420:57779 | EMONITOR | SASSY | | edit delete |

[Enterprise Monitor](#)

[Enterprise Message Viewer](#)

[Message Bank Viewer](#)

[Message Bank Event Log](#)

4. Click the **New Connection**

The page then displays an editing area.

5. Enter the following information:

- **Name** — A convenient short name for this client production. You must specify a value if you want to resend messages to this production.
- **Web IP Address** — The server IP address *and* the web server port used by Ensemble on this server (separated by a colon). For example: `enserver1:57772`
- **Namespace** — Namespace in which the client production is running.
- **Queue Threshold**—The threshold for queues for the Enterprise Monitor.
- **Service Web Application Path** — The URL path to the client's web application for the service `%CSP.Monitor.Server`. The URL path must end with `/` and should not include `http(s)://`. Leave blank to use the default `/csp/namespace/`. For HealthShare, an example could be `/csp/healthshare/namespace/services/`.
- **SOAP Credentials** — Credentials to use for accessing the system. Select the Ensemble credentials created in step 1.
- **SSL Configuration** — SSL configuration to use for viewing messages with the Enterprise Message Viewer or for resending messages from the Enterprise Message Bank.

6. Click **Save**.

7. To edit or delete an existing entry, select “edit” or “delete”.

Note that if you are using the Enterprise Message Bank, when the bank receives a message from a new namespace, it creates an entry for that system. You can edit this entry to add a name, the SOAP credentials, and the SSL configuration so that you can resend messages to this system.

10

Creating Dashboards

This chapter describes how to create dashboards that display Ensemble business metrics. It contains the following topics:

- [Introduction to Dashboards](#)
- [Creating Dashboards](#)
- [Location of Dashboard Definitions](#)
- [For More Information](#)

For information on defining Ensemble business metrics, see [Developing Ensemble Productions](#).

10.1 Introduction to Dashboards


A dashboard displays business metrics or other data (such as DeepSee pivot tables). InterSystems dashboards are web-based. You can display them with the Dashboard Viewer (which is a web page) or you can embed them in Zen pages.

To see the dashboards provided in the ENSDEMO namespace, do the following:

1. In the Management Portal, switch to the ENSDEMO namespace.
2. Click **DeepSee > User Portal** from the Home page. This launches the DeepSee User Portal, which is a separate web-based application.

Note: For your end users, you would probably provide a direct link to the User Portal page.

You then see the DeepSee User Portal (which is intended for general use, despite its specific name). In ENSDEMO, the User Portal looks like this:




The right area of this page lists all dashboards to which you have access. (For workflow users, the right area also includes the Workflow Inbox, with which users display and manage their workflow tasks.)

The left area displays items such as the following:

- Alerts (messages from other users of the User Portal). These are unrelated to Ensemble alerts.
- List of recently accessed dashboards.
- List of dashboards marked as favorites.

The *DeepSee End User Guide* explains how to use this user interface and how to work with dashboards.

If you click the link for a dashboard in the User Portal, the Dashboard Viewer then displays the dashboard. The following shows a simple example:



You create dashboards in the User Portal. If you want users to have access to the User Portal but not have the ability to create their own dashboards, see the chapter “Setting Up Security” in the *DeepSee Implementation Guide*.

You can instead embed individual dashboards in Zen pages. In this case, the users would not need the User Portal. For information, see “Accessing Dashboards from Your Application” in the *DeepSee Implementation Guide*.

10.2 Creating Dashboards

The following is an example procedure of how to create a simple dashboard in DeepSee. Note that not all options you see are described in these steps. (See *Creating DeepSee Dashboards* for full details.)

1. In the ENSDEMO namespace, start the *Demo.Dashboards.Production* from the **Production Configuration** page (**Ensemble > Configure > Productions**).
2. In the Management Portal, click **DeepSee**, click **User Portal**, and then click **Go**.
3. From the **User Portal**, click **New Dashboard** on the **Menu**.

The system displays a dialog box that prompts you for basic information about the new dashboard.

4. For **Dashboard Name**, type the name of the dashboard.
5. Optionally provide values for the following options:

- **Folder** — Specifies the folder, if any, to which the dashboard belongs. You can either type a folder name or select an existing folder. Use the slash character (/) to specify a subfolder. For example, you can enter the following for **Folder**:

`My Folder/My Subfolder`

Folders organize the dashboards as seen in the User Portal.

- **Dashboard Title** — Specifies the title of the dashboard.

If you specify a title, the main area of the User Portal displays the title of the dashboard. Otherwise, it displays the name of the dashboard.

- **Public** — Specifies whether this dashboard is displayed in the User Portal main area.

(Even if the dashboard is not marked as public, you can access it via **Main > Open**. Also, you can find it in the User Portal by using the Find option. See the *DeepSee End User Guide*.)

- **Locked** — Enables you to temporarily prevent changes to this dashboard. If you select this option, you cannot edit the dashboard again unless you first clear the **Locked** option again.
- **Dashboard Owner** — Optionally specifies the Caché user who owns this dashboard. If a dashboard has an owner, then only the owner can specify the **Access Resource** value for the dashboard; see the next item.
- **Access Resource** — Optionally specifies the Caché resource that is used to control access to this dashboard. See the *DeepSee Implementation Guide*.
- **Keywords** — Lists any keywords or phrases to help you find this dashboard later. Enter one keyword or phrase per line; that is, each line you enter here is treated as a single keyword.

These keywords are displayed in the User Portal.

6. Click **OK**.

The system creates, saves, and displays the dashboard, which is initially empty.

7. Click **Add New Widget** on the **Menu** and then click **Bar Chart** on the left from the list of **Pivots and Charts**.
8. Click the magnifying glass to the right of the **Data source**.
9. Click **Business Metrics** on the left of the **Finder Dialog**.

10. Click *Demo.Dashboard.Production* and then *SalesMetrics* to choose this metric as the data source. Click **OK** to add this widget to the dashboard. You now see this widget in the dashboard work space. Resize the widget graphic out so you can see what it contains.
11. Click **Save** on the **Menu** to save the dashboard.
12. Click **Home** to see the list of dashboards and then click the dashboard name you just added to view it.
13. Click the clipboard icon at top left of the bar chart, to edit the appearance of the widget you added using the **Widget Designer**.
14. Click the **Data Properties** tab.
15. Click the plus sign icon at right, click **Sales** in the **Data Value** list, and click **OK**.
16. Click the plus sign icon again, click **Units** in the **Data Value** list, and click **OK**.
17. Click **Save** on the **Menu**.
18. Refresh the browser to see the display change as the production runs.

10.3 Location of Dashboard Definitions

When you create a dashboard, its definition is visible in the Studio **Workspace** window, within the **Other** folder. You can export and import this definition as you do with other items in Studio.

A dashboard definition is not a class definition but can be copied and pasted into a special container class if needed; this container class can contain multiple dashboards and other items. For details, see “Packaging DeepSee Elements into Classes” in the *DeepSee Implementation Guide*.

10.4 For More Information

InterSystems dashboards are documented more fully within the DeepSee documentation. See the following books:

- *Creating DeepSee Dashboards* describes how to create and modify dashboards.
- *DeepSee End User Guide* describes how to work with the User Portal.

Settings in All Productions

This section contains the following sections:

- [Settings in All Productions](#)
- [Settings in All Business Services](#)
- [Settings in All Business Processes](#)
- [Settings in All Business Operations](#)
- [Pool Size and Actor Pool Size](#)
- [Time Stamp Specifications for Filenames](#)

Settings in All Productions

Provides reference information for settings that are available in all productions.

Summary

All productions have the following settings:

| Group | Settings |
|---------------------------|----------------------------------------------------------------------------|
| Informational Settings | Description |
| Basic Settings | Actor Pool Size |
| Additional Settings | Shutdown Timeout , Update Timeout |
| Development and Debugging | Testing Enabled , Log General Trace Events |

Actor Pool Size

Number of system jobs available in a public pool of jobs for use by business processes that have no private pool of jobs. Allow enough for requests to keep moving through the message queues, but no more.

For a full discussion of appropriate pool sizes for different types of production, see the reference section “[Pool Size and Actor Pool Size](#).”

Description

Comments that describe the production.

Log General Trace Events

Trace messages are informational text messages that Ensemble can deliver to the Terminal window and, optionally, to the Ensemble Event Log. Trace messages are unrelated to Visual Trace, which provides a graphical view of Ensemble message objects as they travel through a production.

By default, the **Log General Trace Events** check box is clear. When selected, it enables logging of all trace messages issued by production elements that are *not* business hosts. Logging means that Ensemble automatically stores copies of these trace messages in the Event Log.

Each business host has its own **Log Trace Events** setting, which controls logging of trace messages from that business host. There is no overlap or interaction between these settings. **Log General Trace Events** does not override or provide a default value for **Log Trace Events**.

Shutdown Timeout

How long to wait while attempting to shut down a production before forcing the shutdown. The default is 120 seconds.

Testing Enabled

Select this check box to enable use of the **Ensemble Testing Service** pages to test this production. Clear this check box to disable the testing service.

Update Timeout

How long to wait while attempting to update the configuration for a production that is busy, before abandoning the update. The default is 10 seconds.

Settings in All Business Services

Provides reference information for settings that are available in most or all business services.

Summary

All business services have the following settings:

| Group | Settings |
|---------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Informational Settings | Comment , Category , Class Name , Description , Adapter Class Name , Adapter Description , Business Partner |
| Basic Settings | Enabled |
| Additional Settings | Schedule , Pool Size , Throttle Delay , GenerateSuperSessionID |
| Alerting Control | Alert Grace Period , Alert On Error , Inactivity Timeout |
| Development and Debugging | Foreground , Log Trace Events , Archive IO |

Adapter Class Name

Common to business services and business operations. The class name for the inbound adapter associated with this business host, if any. This field is read-only and is determined by the business host class definition.

Adapter Description

Common to business services and business operations. Comments that describe the adapter class. This field is read-only and displays the first line of the class annotation in the code.

Alert Grace Period

Specifies an optional grace period during which errors relating to external connections do not trigger alerts (even if **Alert On Error** is True). If the error condition still exists after the grace period, the business service triggers an alert; otherwise no alert is triggered.

[Business processes](#) and operations have a similar setting.

Alert On Error

Common to all business hosts. When this setting is set to True, as soon as the business host encounters any type of error condition it automatically triggers an alert. An alert writes a message to the Ensemble Event Log and can also send notification to a user via email or pager. For details, see “[Configuring Alerts](#).”

Archive IO

Common to business services and operations. If True, the adapter associated with this business service or operation logs in the Ensemble I/O archive each input and output communication it shares with the external system.

Business Partner

Common to all business hosts. Specifies an optional business partner applicable to this business host. Select a [business host profile](#), if available.

A business partner profile is information about an organization or application connected to your Ensemble system. For each business partner, you can provide information such as the partner name, notes, primary and alternative contacts, and contact details. Defining a profile has no effect on the behavior or running of the production. It simply gives you a means to store more information.

For example, suppose your production talks to ABC Hospital and XYZ Hospital. You can enter profiles for both of these along with contact information. When you configure items that communicate with these organizations, you can specify the defined business partner for each business host.

For information on defining these profiles, see “[Configuring Business Partners](#),” earlier in this book.

Category

Common to all business hosts. An optional text label that you can use to visually group business hosts within the production diagram. Category names are case-sensitive and can contain space characters.

The **Category** drop-down list contains all the categories that are used in the current production. Specify this setting as follows:

- To specify one category, either type the category name or select it from the **Category** drop-down list. If you type a category name and it does not yet exist, Ensemble creates it.
- To specify multiple categories, select the check box for each desired category from the **Category** drop-down list. Or type a comma-separated list of categories.

To delete a category, remove that category selection from all business hosts that use it. If the **Category** drop-down list still displays the category, that means that the category is still in use. In this case, filter the display to show only business hosts that use that category (see “[Filtering the Display by Category](#),” earlier in this book). Then for each of the business hosts that you see, edit the **Category** to remove the category.

Class Name

Common to all business hosts. The business host class name. This field is read-only.

Comment

Common to all business hosts. An optional text description.

Description

Common to all business hosts. Comments that describe the business host class. This field is read-only and displays the first line of the class annotation in the code.

Enabled

Common to all business hosts. Enables the business host, so that it processes messages whenever the production runs. You can also double-click a business host in the diagram to toggle between enabling and disabling it.

When the **Enabled** check box is clear, the business host is still present in the configuration, and its queue continues to accept messages, but none of these messages are processed until the business host is enabled again.

This setting is useful, for example, if there is a communications breakdown on the external side. For example, if an email server goes down, or something similar happens, you can disable the associated business service until throughput is restored.

Foreground

Common to business services and operations. By default, this check box is clear. Select it for debugging or diagnostic purposes only. Jobs in operational systems almost never run in the foreground. When you select the **Foreground** check box, any system jobs used by the business service run in a Terminal window at the front of the console display. This allows Ensemble to display debugging or trace messages in that window. See “[Testing and Debugging Productions](#)” in *Developing Ensemble Productions*.

Generate SuperSession ID

This property controls whether the message will have a SuperSessionID, which can be used to identify messages that cross from one namespace to another. If this property is set, the business service first checks the inbound message for a SuperSession ID. If it has a SuperSessionID value, it uses it; otherwise, it generates a new SuperSession value. It sets the SuperSession value in the Ensemble message and can also return the value in any response it sends to the caller. The HTTP business services, including the SOAP business service, define how the SuperSessionID is passed in the HTTP headers and handle the SuperSessionID without custom code. For other business services, you must define how the SuperSessionID is represented in the external message and implement the OnGenerateSuperSession callback to process it.

Inactivity Timeout

Common to all business hosts. A business host has an *Inactive* status after it has not received any messages within the number of seconds specified by the **Inactivity Timeout** field. The Ensemble Monitor Service periodically reviews the status of business services and business operations within the production, and marks the item as *Inactive* if it has not done anything within the **Inactivity Timeout** period.

The default value is 0 (zero). If this setting is 0, the business host will never be marked *Inactive*, no matter how long it stands idle.

Log Trace Events

Common to all business hosts. Trace messages are informational text messages that Ensemble can deliver to the Terminal window (if you select the **Foreground** check box) and, optionally, to the Ensemble Event Log. Trace messages are unrelated to Visual Trace, which provides a graphical view of Ensemble message objects as they travel through a production.

By default, the **Log Trace Events** check box is clear. When selected, it enables logging of all trace messages issued by this business host. Logging means that Ensemble writes the trace messages to the console Terminal window (if your job is running in the foreground) and it also stores copies of these messages in the Event Log.

Pool Size

Common to all business hosts. Specifies how many system jobs to allocate to run this business host.

Notes specific to business services:

- For business services, the default is 1.
- You must use a value of 0 if the business service is being invoked via the Ens.Director method **CreateBusinessService()**; this is called an *adapterless* business service.
- You may use a value greater than 1 with File or FTP inbound adapters if you want multiple jobs competing to pull files from the same input directory, or if you have a TCP Service configured with an exclamation point (!) to make it initiate the connection.

For a full discussion of appropriate pool sizes for different types of production, see the reference section “[Pool Size and Actor Pool Size](#).”

Schedule

Common to all business hosts. An optional command string that schedules stop and start times for the business host. The string is a comma-separated list of event specifications, each of which has the following format:

action : YYYY-MM-DDThh:mm:ss

Where *action* is either START or STOP to indicate the desired event. Type a schedule string or select an existing schedule specification.

For details on the schedule string, see “[Configuring Schedule Specifications](#),” earlier in this book.

Throttle Delay

Common to business services and business operations. Specifies a period of forced idleness before processing the next message, in milliseconds. The default is 0.

For a business service, the delay occurs before each call to the adapter's **OnTask()** method. For a business operation, the delay occurs before each attempt to dequeue a new message.

This setting does not apply to SOAP services in CSP mode and other services invoked externally via **CreateBusinessService()**. It applies on a per-job basis so that operations with [Pool Size](#) greater than 1 and services with `JobPerConnection` as true can still generate multiple messages within the interval.

Settings in All Business Processes

Provides reference information for settings that are available in most or all business processes.

Summary

All business processes have the following settings:

| Group | Settings | Notes |
|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------|
| Informational Settings | Comment , Category , Class Name , Description , Business Partner | See these settings for business services |
| Basic Settings | Enabled | See this setting for business services |
| Additional Settings | Schedule , | See this setting for business services |
| | Pool Size , Reply Code Actions , | |
| Alerting Control | Alert Retry Grace Period , Queue Count Alert , Queue Wait Alert | |
| | Alert On Error , Inactivity Timeout | See these settings for business services |
| Development and Debugging | Log Trace Events | See this setting for business services |

Alert Retry Grace Period

Common to business processes and operations. Specifies an optional grace period during which errors relating to external connections do not trigger alerts (even if **Alert On Error** is True).

If the error condition still exists after the alert period expires, the business operation triggers an alert; otherwise no alert is triggered.

[Business services](#) have a similar setting.

Pool Size

Common to all business hosts. See this setting for [business services](#).

Notes specific to business processes:

- A business process shows no pool size if its private pool size is 0 (zero), meaning that it gets its jobs from the public actor pool shared by all business processes in the production.
- This number could be larger to allow higher throughput in some circumstances. If this number is 0, the business process has no private pool of jobs, and uses jobs from the public actor pool for the production.
- Larger numbers are not necessarily helpful; while the potential pool sizes actually range from 0–100, most pool sizes are best set to either 0 or 1, and there can be serious consequences when sizes are set to a number greater than 1.

Important: When you disable a business process, it must have a **Pool Size** = 1 or greater if you want all instances of only this business process to stop. If the business process has a **Pool Size** = 0, the action disables all business processes that share the actor pool. See the reference section “[Pool Size and Actor Pool Size](#).”

Queue Count Alert

Common to business processes and operations. Specifies an alert threshold for the number of items in the queue of this business host.

Ensemble sends an alert when the number of items in a business host's queue reaches the threshold set by this setting for that business host. This alert has the prefix `QueueCountAlert:` (not localized). This alert is to detect large queues that are building up.

The service that checks the queue count runs every five seconds, so the granularity of the checking is somewhat limited, but should still provide timely warnings about processing and flow problems.

To disable this alert, specify this setting as 0.

For information on alerts, see “[Configuring Alerts](#).”

Queue Wait Alert

Common to business processes and operations. Specifies an alert threshold for the wait time of the queue of this business host.

Ensemble sends an alert when a message has been in a business host's queue for the length of time specified by this setting for that business host. This alert has the prefix `QueueWaitAlert:` (not localized). This alert is useful to detect whether a queue is processing messages.

The service that checks the wait periods runs every five seconds, so the granularity of the checking is somewhat limited, but should still provide timely warnings about processing and flow problems.

To disable this alert, specify this setting as 0.

For information on alerts, see “[Configuring Alerts](#).”

Reply Code Actions

Common to business processes and business operations. Comma-separated list of code-action pairs, specifying which action the business process takes on receipt of various reply status conditions.

The **Reply Code Actions** setting allows you to supply a comma-separated list of code-action pairs, specifying which action the business host takes on receipt of various reply status conditions. The format of the list is:

code=actions , (code,code)=actions , ... code=action

The following table lists the types of reply status condition identified by *code*.

| Code | Meaning |
|----------------------|-----------------------------------------------------------------------------------------|
| E | Error status returned from message handler. |
| E# <i>statusCode</i> | Error status returned from message handler has status code equal to <i>statusCode</i> . |
| E* <i>text</i> | Error status returned from message handler contains text string <i>text</i> . |
| X | There is no reply message object at all. |

The following values for *action* may be used alone or combined to form strings.

| Action | Meaning |
|--------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| C | Treat the document as <i>Completed OK</i> . |
| W | Log a warning but treat the document as <i>Completed OK</i> . |
| R | Retry the message according to the configured Retry Interval and Failure Timeout settings; finally <i>Fail</i> , unless a different action is also specified. |

| Action | Meaning |
|--------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| S | Suspend the message, log an error, and move on to try the next message (the default). |
| D | <p>Disable the business process or operation, log an error, and restore the outbound message to the front of the business host queue.</p> <p>When you choose the disable action for a business process, you must configure the business with a Pool Size = 1 or greater if you want all instances of only this business process to stop. If the business process has a Pool Size = 0, the disable action disables all business processes that share the actor pool. See “Pool Size and Actor Pool Size.”</p> |
| F | Fail with an error and move on to try the next message. |

For example:

```
E#6301=R,E*ErrGeneral=R,E=F
```

The default value for the **Reply Code Actions** string is:

```
E=F
```

Which means when there is an error, fail and move on to try the next message.

All codes where the *actions* consists of only W (log a Warning) are evaluated and warnings generated if they trigger. Other codes are evaluated in left-to-right order, executing the first one that triggers that has a non-warning *actions* value. For example if the reply code action has the value E=RD, the business process or operation first retries to send the message until **Failure Timeout** setting and then, if the failure continues, it disables the business process or operation.

Settings in All Business Operations

Provides reference information for settings that are available in all business operations.

Summary

All business operations have the following settings:

| Group | Settings | Notes |
|---------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------|
| Informational Settings | Comment , Category , Class Name , Description , Adapter Class Name , Adapter Description , Business Partner | See these settings for business services |
| Basic Settings | Enabled | |
| Additional Settings | Schedule , Pool Size | |
| | Reply Code Actions | See this setting for business processes |
| | Retry Interval , Failure Timeout | |
| | SendSuperSession | |
| | Throttle Delay | See this setting for business services |
| Alerting Control | Alert Retry Grace Period | |
| | Queue Count Alert , Queue Wait Alert | See these settings for business processes |
| | Alert On Error , Inactivity Timeout | See these settings for business services x |
| Development and Debugging | Foreground , Log Trace Events , Archive IO | |

Alert Retry Grace Period

Common to business processes and operations. Specifies an optional grace period during which errors relating to external connections do not trigger alerts (even if **Alert On Error** is True).

If the error condition still exists after the alert period expires, the business operation triggers an alert; otherwise no alert is triggered.

[Business services](#) have a similar setting.

Failure Timeout

Total number of seconds to keep trying to connect with a destination outside Ensemble. After this number of seconds has elapsed, the business operation discards the message data and returns an error code. To ensure that no message is ever skipped, enter a **Failure Timeout** value of **-1**, which means “never time out.” Use a setting of **-1** when complete data delivery is critical, for example in healthcare applications.

Retry Interval

Number of seconds to wait between attempts to connect with a destination outside Ensemble.

SendSuperSession

The `SendSuperSession` property controls whether outbound adapters include the `SuperSession` property in the outgoing message. The `SuperSession` property is used to associate messages that cross from one namespace to another. The HTTP and SOAP outbound adapters support `SuperSession` and automatically write the `SuperSession` value to the outgoing HTTP header. Although the other outbound adapters do not automatically support `SuperSession`, you can add custom code that inserts the `SuperSession` value into the outgoing message. For details, see “[SendSuperSession](#)” in *Using HTTP Adapters with Ensemble*.

Pool Size and Actor Pool Size

Provides conceptual and reference information for the **Pool Size** and **Actor Pool Size** settings.

Introduction

The choice of **Actor Pool Size** for the production, and **Pool Size** for each business host, determines how many jobs are available to perform which types of work for the production. These numbers are an essential part of the production design and are unlikely to need adjustment once the production is deployed live. Larger numbers are not necessarily helpful; most pool sizes are best set to either 0 or 1, and there can be serious consequences when sizes are set to a number greater than 1.

Private Pool Size for Business Hosts

Each business service, business process, or business operation can have its own, private pool of allocated jobs. You can configure the size of this pool in the Management Portal. If in testing your production, you find that you need more than 100 jobs per business host, it may indicate some other kind of problem, such as a bottleneck or deadlock that you should address. If it is a computational bottleneck, then there is no point in having the pool size larger than the number of CPUs.

Ensemble uses a **Pool Size** of 0 for an *adapterless* business service. This is a business service that is invoked directly from outside Ensemble, rather than receiving its requests in the usual way, via an inbound adapter. An adapterless business service may be invoked via Caché language bindings, CSP pages, SOAP, or a routine invoked from the operating system level. For details, see “[Invoking a Business Service Directly](#)” in *Developing Ensemble Productions*.

If you set a business operation to run *in process* as opposed to *queued*, Ensemble does not create a background job or message queue for the business operation. Instead, whenever a request is sent to this business operation, Ensemble instantiates the business operation *within the caller's job*, and invokes its methods within that job, as well. Consequently, no job pool is necessary, and you must set the business operation **Pool Size** to 0.

For all other types of business service or business operations, if you set the **Pool Size** to 0, the business host does not run.

Production Actor Pool Size for Business Processes

Unlike other types of business host, a *business process* has the option of sharing jobs from a public pool; this pool is called the *actor pool* or **Ens.Actor**. You can configure the **Actor Pool Size** for the production. Actors in the production-wide actor pool have no affiliation with or knowledge of a specific business process. Any business process that has a private **Pool Size** of 0 can use jobs from the public actor pool.

The choice as to whether or not a business process should use its own private pool or the public pool depends on the needs of the production. Any nonzero value for a private **Pool Size** ensures that the business process only uses jobs from its private pool. If you want any business process to use jobs from the actor pool, its private **Pool Size** *must* be 0. The default Ensemble configuration allows 1 job in the private pool for each business host, and 2 jobs in the production-wide actor pool. This means that if you want business processes to share the actor pool it does not happen automatically; you must set their individual **Pool Size** settings to 0.

When you disable a business process, the result depends on the private **Pool Size** configuration setting:

- **Business process Pool Size > 0:**

The business process only uses jobs from its private pool; you can disable just this process by clearing the **Enabled** check box on the configuration page of the business process.

- **Business process Pool Size = 0:**

The portal will set the pool size of the business process to 1 before disabling it. Typically, the portal displays a message warning you about this action before taking this action. If a business process with a pool size of 0 is disabled, it stops all business processes using the shared actor pool, which is why the portal does not allow this change. If you do want to stop all business processes using the shared actor pool, set the **Actor Pool Size** to 0 in the production settings tab.

First-In First-Out (FIFO) for Healthcare

A private **Pool Size** of 1 makes first-in, first-out (*FIFO*) processing possible. If all the business hosts in the production have only one job available, only one message can be processed at a time by each host. This gives each message from a given source only one possible path through the production, so each message is guaranteed to arrive at its configured destination in the same order in which it was sent. Without guaranteed FIFO, a message from a particular source could *skip over* other messages from the same source by using a faster, parallel job to arrive at its destination sooner.

For this reason, InterSystems recommends that every business service, business process, and business operation in a message routing production for healthcare has its **Pool Size** setting configured to 1, with the **Actor Pool Size** for the production at 0.

To guarantee FIFO for a business process, in addition to setting its **Pool Size** to 1, either

1. Make calls using a `SendRequestSync()` call

OR

2. Do not make calls from conditional branches of your business process logic *and* only make calls to elements that are themselves FIFO.

FIFO is essential for healthcare applications. Suppose a patient enters a hospital and requires care. System A sends out an admit event, followed by a treatment order, but System B receives the order first. System B cannot process the order without an admit, so upon receiving the order, it produces an error. This may delay patient care or require the information system to execute complex logic to associate admit with the order after the admit finally arrives at System B.

Considerations and Trade-offs

In situations other than healthcare, private pools of a size 1 or greater can be useful for fast-running business processes in a production that also includes slow-running business processes. A fast-running business process can have a private pool to ensure that its requests never get stuck in the public actor queue behind accumulated requests for the slow-running business processes.

If every business process in your production has a private pool, then the **Actor Pool Size** for the production can be 0. On the other hand, if your production includes many business processes that use the public actor pool, you can raise the **Actor Pool Size** for the production from the default of 2 to prevent bottlenecks when many business processes are running. InterSystems recommends that, as a maximum, you set the **Actor Pool Size** equal to the number of CPUs in your Ensemble server machine. You could set the number higher, but at any one time there are only as many jobs available as there are CPUs.

Time Stamp Specifications for Filenames

Provides reference information for time stamp specifications for filenames.

Details

While configuring business operations and business services that transmit data to and from files, you can often specify input and output filenames in a string that includes date and time format codes, such as %Y%M%d%h%m%s_%f.txt. At runtime, the format codes within this string resolve dynamically based on the current date and time.

Ensemble supports the following rules for composing a *time stamp specification string*:

- The string may contain literal characters and any of the format codes listed in the following table.
- Characters that are not part of a format code appear in the resulting time stamp unchanged.
- All format codes are optional.
- Each format code consists of a % character, an optional # character, and a conversion character.
- Ensemble converts the time to a specific time zone or locale if the %K or %L format codes appear at the beginning of the string.

| Symbol | Meaning Within a Filename Specification |
|--------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| %a | Locale's abbreviated weekday name (Sun, Mon, ..., Sat) |
| %A | Locale's full weekday name (Sunday, Monday, ..., Saturday) |
| %b | Locale's abbreviated month name (Jan, Feb, ..., Dec) |
| %B | Locale's full month name (January, February, ..., December) |
| %c | <p>Caché date and time representation as provided by the local machine, except that in forming the time stamp, Ensemble replaces certain characters in the usual date and time format. It replaces spaces with underscores (_), slashes (/) with hyphens (-), and colons (:) with dots (.).</p> <p>The result is something like:</p> <p>MM-DD-YY_hh.mm.ss</p> <p>The %c specifier can have parameters. %c(<i>dformat</i>,<i>tformat</i>,<i>precision</i>) formats the date and time according to your specifications, where:</p> <ul style="list-style-type: none"> • <i>dformat</i> is a number indicating date format. • <i>tformat</i> is a number indicating time format. • <i>precision</i> is the number of decimal places used to represent subseconds. <p>The <i>Caché ObjectScript Reference</i> describes the %c parameters <i>dformat</i>, <i>tformat</i>, and <i>precision</i> in detail. See the \$ZDATETIME topic for a list of all possible <i>dformat</i> and <i>tformat</i> values.</p> |
| %d | Two digits indicating the day of the month (01-31) |
| %#d | Day of the month without leading zeros (1-31) |
| %D | Date; equivalent to %m/%d/%y |
| %#D | Date; equivalent to %#m/%#d/%y |

| Symbol | Meaning Within a Filename Specification |
|--------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| %f | Name indicating the source of the data. The source is usually the input filename (for File and FTP) or a concatenation of the IP address and port number (for data that arrived via TCP). In substituting a value for the format code %f, Ensemble strips out any of the characters ,?,\,/,.,:,[,],<,>,&,,,NUL,BEL,TAB,CR,LF, replacing spaces with underscores (_), slashes (/) with hyphens (-), and colons (:) with dots (.). |
| %#f | Only use the part of the input filename up to but not including the last period. For example: <ul style="list-style-type: none"> With Input filename “Summary.docx”, %#f is replaced with “Summary”. With input filename “MyData.txt.dat”, %#f is replaced with “MyData.txt”. |
| ;%f | Only use the part of the input file name from the last period to the end of the filename (the file extension). For example, if the input filename is “MyData.txt.dat”, %f is replaced with “.dat”. |
| %F | As for %f, but with all alphabetic characters converted to uppercase. |
| %#F | As for %#f, but with all alphabetic characters converted to uppercase. |
| ;%F | As for %f, but with all alphabetic characters converted to uppercase. |
| %h | Locale’s abbreviated month name. Equivalent to %b. |
| %H | Two digits indicating the hour in 24-hour format (00-23) |
| %#H | Hour in 24-hour format without leading zeros (0-23) |
| %l | Two digits indicating the hour in 12-hour format (01-12) |
| %#l | Hour in 12-hour format without leading zeros (1-12) |
| %j | Three digits indicating the day of the year as a number (001-366) |
| %#j | Day of the year as a number without leading zeros (1-366) |
| %K(n) | Use the %K(n) format code only at the beginning of the time stamp specification string. %K(n) produces no output, but specifies a base time zone to convert to before formatting the time stamp. <i>n</i> is the time zone, and can be one of the following (case-insensitive): <ul style="list-style-type: none"> Server — (Default) Time on the server where the executing code resides. UTC — Universal Time Coordinated (UTC) [+]<i>n</i> — Number of hours after (east of) UTC time. <i>n</i> may have a fractional value expressed as a decimal; for example, 4.5 -<i>n</i> — Number of hours before (west of) UTC time (<i>n</i> may be fractional) [+]<i>hhmm</i> — Hours and minutes after (east of) UTC time, in the ISO 8601:2000 standard format -<i>hhmm</i> — Hours and minutes after (west of) UTC time in ISO format |
| %m | Two digits indicating the month number (01-12) |
| %#m | Month number without leading zeros (1-12) |
| %M | Two digits indicating minutes (00-59) |
| %#M | Minutes without leading zeros (0–59) |

| Symbol | Meaning Within a Filename Specification |
|------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| %N | Three digits indicating the number of milliseconds (000-999) |
| %p | Locale's a.m. or p.m. indicator for a 12-hour clock (lowercase, with dots) |
| %#p | Locale's am or pm indicator for 12-hour clock (lowercase, without dots) |
| %P | Locale's A.M. or P.M. indicator for a 12-hour clock (uppercase, with dots) |
| %#P | Locale's AM or PM indicator for a 12-hour clock (uppercase, without dots) |
| %q or %q() | HL7 format date and time; equivalent to %Y%m%d%H%M%S or %q(0) |
| %q(0) | HL7 format date and time; equivalent to %Y%m%d%H%M%S or %q |
| %q(1) | ODBC format date and time; equivalent to %Y-%m-%d %H:%M:%S.%N |
| %q(2) | ISO 8601:2000 standard date format; equivalent to %Y-%m-%d |
| %q(3) | Caché \$HOROLOGY format |
| %q(4) | Caché \$ZTIMESTAMP format |
| %q(5) | Creates a GUID |
| %Q | ODBC format date and time; equivalent to %Y-%m-%d %H:%M:%S.%N or %c(3,,3) or %q(1) |
| %Q(n) | Equivalent to %q(n) |
| %r | Time with seconds in 12-hour format using a.m. or p.m. notation; equivalent to %l:%M:%S %p |
| %#r | Time with seconds in 12-hour format using am or pm notation without whitespace or dots; equivalent to %l:%M:%S%#p |
| %R | Time in 24-hour notation; equivalent to %H:%M |
| %S | Two digits indicating seconds (00-60) (60 for leap seconds) |
| %t | Produces a <tab> character |
| %T | Time with seconds in 24-hour notation; equivalent to %H:%M:%S |
| %u | Day of the week as a number (1-7). Monday=1, Tuesday=2, ..., Sunday=7. |
| %#u | Equivalent to %u |
| %U | Two digits (00–53) indicating the current week within a week-based year convention that does not conform to the ISO 8601:2000 standard. The rules are as follows: <ul style="list-style-type: none"> • The week numbers are 00-53 • Sunday is the first day in each week. • The first Sunday of January is the first day of week 1 • Days in the new year before the first Sunday are in week 0. |
| %#U | Number indicating the current week within a week-based year that follows the rules described for %U, except the output does not include leading zeros (0-53). |
| %w | Day of the week (Sunday=0, Monday=1, ..., Saturday=6) |

| Symbol | Meaning Within a Filename Specification |
|--------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| %#w | Equivalent to %w |
| %W | <p>Two digits (00–53) indicating the current week within a week-based year convention that does not conform to the ISO 8601:2000 standard.</p> <p>The rules are as follows:</p> <ul style="list-style-type: none"> • The week numbers are 00-53 • Monday is the first day in each week • The first Monday of January is the first day of week 1 • Days in the new year before the first Monday are in week 0. <p>%W is equivalent to %U(1).</p> |
| %#W | Number indicating the current week within a week-based year that follows the rules described for %W, except the output does not include leading zeros (0-53). %#W is equivalent to %#U(1). |
| %y | Two digits indicating the year within a century (00-99). For example, the year 1983 produces the number 83 in the time stamp; 2019 produces 19. |
| %Y | Four digits indicating the year (0000-9999) |
| %z | Time zone as an offset from Universal Time Coordinated (UTC) in the ISO 8601:2000 standard format (+ <i>hhmm</i> or - <i>hhmm</i>). For example, -0430 means 4 hours 30 minutes behind UTC (west of Greenwich). If Ensemble cannot determine the time zone, it ignores the %z code in the time stamp specification string. |
| %#z | Time zone as an offset from Universal Time Coordinated (UTC) in hours with leading +/- and without leading zeros. Trailing decimals may appear. For example, -4.5 means 4 hours 30 minutes behind UTC (that is, west of Greenwich). If Ensemble cannot determine the time zone, it ignores the %#z code in the time stamp. |

| Symbol | Meaning Within a Filename Specification |
|---------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>%+(nn)</code> | <p>Inserts a counter and tests for filename uniqueness on a local file (not FTP) where <i>nn</i> is a string of alphanumerics and other characters. The alphanumeric characters in the string are incremented from the right-most character. Nonalphanumeric characters are included unchanged in the output file specification. Numeric characters are incremented from 0 to 9 and alphabetic characters are incremented from a to z or from A to Z.</p> <p>For example, if the filename string specification is <code>“%f_%+(1)”</code> and the input file is <code>“NewFile.txt”</code>, then Ensemble first checks if <code>“NewFile.txt_1”</code> exists. If it exists, it checks <code>“NewFile.txt_2”</code> through <code>“NewFile.txt_9”</code> and then <code>“NewFile.txt_10”</code> and so on. It creates the file with the first filename that doesn’t yet exist.</p> <p>If the filename string is <code>“%f_%+(a.1)”</code>, it first increments the 1 digit and then, after reaching 9, it increments the a; first testing the strings <code>“NewFile.txt_a.1”</code> through <code>“NewFile.txt_a.9”</code> and then <code>“NewFile.txt_b.0”</code> through <code>“NewFile.txt_b.9”</code> and then <code>“NewFile.txt_c.0”</code> and so on. After it reaches <code>“NewFile.txt_z.9”</code>, it prepends an 1 to the string. In this case, it tests <code>“NewFile.txt_1a.0”</code> next.</p> <p>Typically, the counter is used in conjunction with a timestamp to reduce the possibility that filenames are duplicates even if they are created with the same timestamp. Combining a timestamp with a counter makes it extremely unlikely that filename collisions will occur.</p> <p>You can use the <code>%+</code> counter specification only once within a filename specification.</p> <p>The counter format can be modified by inserting any of the following symbols between the percent sign and the plus sign:</p> <ul style="list-style-type: none"> Dollar sign (\$)—Allows the counter to be used for remote FTP filenames. Always increment a static counter and use the resulting value. For local files, the uniqueness check is then made. Exclamation point (!)—Only append the counter if the filename without the counter would not be unique. Number sign (#)—Omit leading zeroes and omit leading a’s if they are not required to make a unique filename. <p>If the dollar sign (\$) is not specified, the counter always restarts from the initial value specified in <i>nn</i>. If used with a timestamp, the counter is typically incremented a small number of times before a new timestamp value ensures uniqueness. If you are using the counter without a timestamp and expect it to be incremented many times, you should specify the dollar sign to avoid continually rechecking the filenames that you have already created.</p> <p>Consider the format <code>“%#F_%Q_%+(a0)%\$f”</code>. If the input filename is <code>“NewFile.txt”</code> and three files are created with the same timestamp, these files are named:</p> <ul style="list-style-type: none"> <code>NEWFILE_2014-09-12_16.43.15.895_a0.txt</code> <code>NEWFILE_2014-09-12_16.43.15.895_a1.txt</code> <code>NEWFILE_2014-09-12_16.43.15.895_a2.txt</code> |
| <code>%%</code> | Literal % percent sign |
| <code>% (</code> | Literal (left parenthesis |
| <code>%_</code> | Reserved token (do not use). This sequence passes through unchanged. |

The previous table describes all the format codes that you can use when specifying time stamps for use with an inbound or outbound file adapter. These codes conform to POSIX, IEEE, and ISO standards for time format codes. The following table lists the time stamp format codes that do not conform to these standards, or that conform to other standards.

| Symbol | Unique Meaning Within a Filename Specification |
|----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| %# | Ensemble supports (and extends) certain Microsoft extended semantics, such as the %# prefix. |
| %c | This indicates the Caché time stamp provided by the local machine. |
| %E | Ensemble does not support the %E code. |
| %F | Ensemble supports %F as an uppercase replacement string, not an ISO format date. Ensemble supports the ISO format date as %q(2) or %Q(2). |
| %K(<i>n</i>) | The user defines the time zone by providing the %K(<i>n</i>) code at the beginning of the file specification string. The %K(<i>n</i>) code produces no output, but specifies a base time zone to convert to before formatting the time stamp. |
| %L(<i>n</i>) | The user defines the locale by providing the %L(<i>n</i>) code at the beginning of the file specification string. The %L(<i>n</i>) code produces no output, but specifies a base locale to use with locale-dependent format codes. |
| %O | Ensemble does not support the %O code. |
| %P | Ensemble defines this code as uppercase AM or PM. |
| %q,%Q | Ensemble defines some of these codes according to standards other than POSIX, IEEE, or ISO, such as HL7 or ODBC. |
| %(<i></i> | Ensemble defines this code as a literal (character. |

